



*Full credit is given to the above companies including the OS that this PDF file was generated!*

## ***Rocky Enterprise Linux 9.2 Manual Pages on command 'systemd-gpt-auto-generator.8'***

***\$ man systemd-gpt-auto-generator.8***

SYSTEMD-GPT-AUTO-GENERATORsystemd-gpt-auto-generaSYSTEMD-GPT-AUTO-GENERATOR(8)

### NAME

systemd-gpt-auto-generator - Generator for automatically discovering and mounting root, /home/, /srv/, /var/ and /var/tmp/ partitions, as well as discovering and enabling swap partitions, based on GPT partition type GUIDs

### SYNOPSIS

/usr/lib/systemd/system-generators/systemd-gpt-auto-generator

### DESCRIPTION

systemd-gpt-auto-generator is a unit generator that automatically discovers root, /home/, /srv/, /var/, /var/tmp/, the EFI System Partition, the Extended Boot Loader Partition and swap partitions and creates mount and swap units for them, based on the partition type GUIDs of GUID partition tables (GPT), see UEFI Specification[1], chapter 5. It implements the Discoverable Partitions Specification[2]. Note that this generator has no effect on non-GPT systems, and on specific mount points that are directories already containing files. Also, on systems where the units are explicitly configured (for

example, listed in `fstab(5)`, the units this generator creates are overridden, but additional implicit dependencies might be created. This generator will only look for the root partition on the same physical disk where the EFI System Partition (ESP) is located. Note that support from the boot loader is required: the EFI variable `LoaderDevicePartUUID` of the `4a67b082-0a4c-41cf-b6c7-440b29bb8c4f` vendor UUID is used to determine from which partition, and hence the disk from which the system was booted. If the boot loader does not set this variable, this generator will not be able to autodetect the root partition. See the `Boot Loader Interface[3]` for details.

Similarly, this generator will only look for the other partitions on the same physical disk as the root partition. In this case, boot loader support is not required. These partitions will not be searched for on systems where the root file system is distributed on multiple disks, for example via `btrfs RAID`.

`systemd-gpt-auto-generator` is useful for centralizing file system configuration in the partition table and making configuration in `/etc/fstab` or on the kernel command line unnecessary.

This generator looks for the partitions based on their partition type GUID. The following partition type GUIDs are identified:

Table 1. Partition Type GUIDs

Partition Type	Name	Mount Point	Explanation
44f68bce3-e8cd-4db1-96e7-fbcaf984b709 (x86-64)	Root Partition	/	The first partition with this type UUID, located on the same disk as the ESP, is used as











means of an automount point, similar to the ESP, see above). If both an EFI System Partition and an Extended Boot Loader partition exist the latter is preferably mounted to `/boot/`. Make sure to create both `/efi/` and `/boot/` to ensure both partitions are mounted.

When using this generator in conjunction with btrfs file systems, make sure to set the correct default subvolumes on them, using `btrfs subvolume set-default`.

`systemd-gpt-auto-generator` implements `systemd.generator(7)`.

## KERNEL COMMAND LINE

`systemd-gpt-auto-generator` understands the following kernel command line parameters:

`systemd.gpt_auto`, `rd.systemd.gpt_auto`

Those options take an optional boolean argument, and default to yes. The generator is enabled by default, and a negative value may be used to disable it.

`root=`

When used with the special value "gpt-auto", automatic discovery of the root partition based on the GPT partition type is enabled. Any other value disables this generator.

`rw`, `ro`

Mount the root partition read-write or read-only initially.

Note that unlike most kernel command line options these settings do not override configuration in the file system, and the file system may be remounted later. See `systemd-remount-fs.service(8)`.

## SEE ALSO

`systemd(1)`, `systemd.mount(5)`, `systemd.swap(5)`, `systemd-fstab-generator(8)`, `systemd-cryptsetup@.service(8)`, `machine-id(5)`, `cryptsetup(8)`, `fstab(5)`, `btrfs(8)`

## NOTES

### 1. UEFI Specification

<https://uefi.org/specifications>

### 2. Discoverable Partitions Specification

[https://systemd.io/DISCOVERABLE\\_PARTITIONS](https://systemd.io/DISCOVERABLE_PARTITIONS)



### 3. Boot Loader Interface

[https://systemd.io/BOOT\\_LOADER\\_INTERFACE](https://systemd.io/BOOT_LOADER_INTERFACE)

### 4. Boot Loader Specification

[https://systemd.io/BOOT\\_LOADER\\_SPECIFICATION](https://systemd.io/BOOT_LOADER_SPECIFICATION)

systemd 252

SYSTEMD-GPT-AUTO-GENERATOR(8)