PowerShell Get-Help on command 'Add-MpPreference'

PS C:\Users\wahid> Get-Help Add-MpPreference

NAME

    Add-MpPreference

SYNTAX

    Add-MpPreference [-ExclusionPath <string[]>] [-ExclusionExtension <string[]>]

    [-ExclusionProcess <string[]>] [-ExclusionIpAddress <string[]>]

    [-ThreatIDDefaultAction_Ids <long[]>] [-ThreatIDDefaultAction_Actions {Clean |

    Quarantine | Remove | Allow | UserDefined | NoAction | Block}]

    [-AttackSurfaceReductionOnlyExclusions <string[]>]

    [-ControlledFolderAccessAllowedApplications <string[]>]

    [-ControlledFolderAccessProtectedFolders <string[]>]

    [-AttackSurfaceReductionRules_Ids <string[]>]

    [-AttackSurfaceReductionRules_Actions {Disabled | Enabled | AuditMode |

    NotConfigured | Warn}] [-AttackSurfaceReductionRules_RuleSpecificExclusions_Id

    <string[]>] [-AttackSurfaceReductionRules_RuleSpecificExclusions <string[]>]

    [-RemoteEncryptionProtectionExclusions <string[]>]

    [-BruteForceProtectionExclusions <string[]>] [-Force] [-CimSession

    <CimSession[]>] [-ThrottleLimit <int>] [-AsJob] [<CommonParameters>]

PARAMETERS

-AsJob

-AttackSurfaceReductionOnlyExclusions <string[]>

-AttackSurfaceReductionRules_Actions <ASRRuleActionType[]>

-AttackSurfaceReductionRules_Ids <string[]>

-AttackSurfaceReductionRules_RuleSpecificExclusions <string[]>

-AttackSurfaceReductionRules_RuleSpecificExclusions_Id <string[]>

-BruteForceProtectionExclusions <string[]>

-CimSession <CimSession[]>

-ControlledFolderAccessAllowedApplications <string[]>

-ControlledFolderAccessProtectedFolders <string[]>

-ExclusionExtension <string[]>

-ExclusionIpAddress <string[]>

-ExclusionPath <string[]>

-ExclusionProcess <string[]>

-Force

-RemoteEncryptionProtectionExclusions <string[]>

-ThreatIDDefaultAction_Actions <ThreatAction[]>

-ThreatIDDefaultAction_Ids <long[]>

-ThrottleLimit <int>

<CommonParameters>
    This cmdlet supports the common parameters: Verbose, Debug,

    ErrorAction, ErrorVariable, WarningAction, WarningVariable,

    OutBuffer, PipelineVariable, and OutVariable. For more information, see

    about_CommonParameters (https:/go.microsoft.com/fwlink/?LinkID=113216).

ALIASES

    None

REMARKS

    Get-Help cannot find the Help files for this cmdlet on this computer. It is

    displaying only partial help.

        -- To download and install Help files for the module that includes this

    cmdlet, use Update-Help.