Windows PowerShell Get-Help on Cmdlet 'Remove-AzStackHCIVMAttestation'

PS:\>Get-HELP Remove-AzStackHCIVMAttestation -Full

NAME

    Remove-AzStackHCIVMAttestation

SYNOPSIS

    Remove-AzStackHCIVMAttestation removes guests from AzureStack HCI IMDS Attestation.

SYNTAX

    Remove-AzStackHCIVMAttestation [-VMName] <String[]> [-Force] [-WhatIf] [-Confirm] [<CommonParameters>]

    Remove-AzStackHCIVMAttestation [-Force] [-VM] <Object[]> [-WhatIf] [-Confirm] [<CommonParameters>]

    Remove-AzStackHCIVMAttestation [-Force] -RemoveAll [-WhatIf] [-Confirm] [<CommonParameters>]

DESCRIPTION

    Remove-AzStackHCIVMAttestation removes guests from AzureStack HCI IMDS Attestation.

PARAMETERS

-VMName <String[]>

    Specifies an array of guest VMs to enable.

    Required?   true

    Position?   1

    Default value

    Accept pipeline input?   true (ByValue)

    Accept wildcard characters? false

-Force [<SwitchParameter>]

    No confirmations.

    Required?   false

    Position?   named

    Default value   False

    Accept pipeline input?   false

    Accept wildcard characters? false

-VM <Object[]>

    Specifies an array of VM objects from Get-VM.

    Required?   true

    Position?   1

    Default value

    Accept pipeline input?   true (ByValue)

    Accept wildcard characters? false

-RemoveAll [<SwitchParameter>]

    Specifies a switch that will remove all guest VMs from Attestation on the current node

    Required?   true

    Position?   named

    Default value   False

Accept pipeline input?   false

Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required?   false

Position?   named

Default value

Accept pipeline input?   false

Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required?   false

Position?   named

Default value

Accept pipeline input?   false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see

about_CommonParameters (https:/go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

System.Object[]

System.String[]

OUTPUTS

System.Management.Automation.PSObject

-------------------------- EXAMPLE 1 --------------------------

PS C:\>Remove-AzStackHCIVMAttestation -RemoveAll

RELATED LINKS

https://learn.microsoft.com/powershell/module/az.stackhci/remove-azstackhcivmattestation