



Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'XtAppSetWarningMsgHandler.3'

\$ man XtAppSetWarningMsgHandler.3

XtAppErrorMsg(3)

XT FUNCTIONS

XtAppErrorMsg(3)

NAME

XtAppErrorMsg, XtAppSetErrorHandler, XtAppSetWarningMsgHandler, XtAppWarningMsg - high-level error handlers

SYNTAX

```
#include <X11/Intrinsic.h>
```

```
void XtAppErrorMsg(XtApplicationContext app_context, const char *name, const char *type, const
char *class, const char *defaultMsg, String *params, Cardinal *num_params);
```

```
XtErrorHandler XtAppSetErrorHandler(XtApplicationContext app_context, XtErrorHandler
msg_handler);
```

```
XtErrorHandler XtAppSetWarningMsgHandler(XtApplicationContext app_context, XtErrorHandler
msg_handler);
```

```
void XtAppWarningMsg(XtApplicationContext app_context, const char *name, const char *type, const
char *class, const char *defaultMsg, String *params, Cardinal *num_params);
```

ARGUMENTS

app_context

Specifies the application context.

class Specifies the resource class of the error message.

defaultMsg

Specifies the default message to use.

name Specifies the general kind of error.

type Specifies the detailed name of the error.

msg_handler

Specifies the new fatal error procedure, which should not return or the nonfatal error procedure, which usually returns.

num_params

Specifies the number of values in the parameter list.

params Specifies a pointer to a list of values to be stored in the message.

DESCRIPTION

The XtAppErrorMsg function calls the high-level error handler and passes the specified information.

The XtAppSetErrorHandler function registers the specified procedure, which is called when a fatal error occurs.

The XtAppSetWarningMsgHandler function registers the specified procedure, which is called when a nonfatal error condition occurs.

The XtAppWarningMsg function calls the high-level error handler and passes the specified information.

SEE ALSO

[XtAppGetErrorHandler\(3\)](#), [XtAppError\(3\)](#)

[X Toolkit Intrinsics - C Language Interface](#)

[Xlib - C Language X Interface](#)

X Version 11

libXt 1.2.1

[XtAppErrorMsg\(3\)](#)