

# Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

# Rocky Enterprise Linux 9.2 Manual Pages on command 'mv.1'

\$ man mv.1			
Mν	/(1)	User Commands	MV(1)
NAME			
	mv - move (rename) files		
SYNOPSIS			
	mv [OPTION] [-T] SO	JRCE DEST	
	mv [OPTION] SOURCE DIRECTORY		
	mv [OPTION]t DIRE	CTORY SOURCE	
DESCRIPTION			
	Rename SOURCE to DEST, or move SOURCE(s) to DIRECTORY.		
	Mandatory arguments to long options are mandatory for short options too.		
	backup[=CONTROL]		
	make a backup of e	each existing destination file	
	-b likebackup but d	oes not accept an argument	
	-f,force		
	do not prompt befor	re overwriting	
	-i,interactive		
	prompt before over	write	
	-n,no-clobber		
	do not overwrite an	existing file	
	If you specify more than one of -i, -f, -n, only the final one takes effect.		
	strip-trailing-slashes		

remove any trailing slashes from each SOURCE argument

-S, --suffix=SUFFIX

override the usual backup suffix

-t, --target-directory=DIRECTORY

move all SOURCE arguments into DIRECTORY

-T, --no-target-directory

treat DEST as a normal file

-u, --update

move only when the SOURCE file is newer than the destination file or when the des?

tination file is missing

-v, --verbose

explain what is being done

-Z, --context

set SELinux security context of destination file to default type

--help display this help and exit

#### --version

output version information and exit

The backup suffix is '~', unless set with --suffix or SIMPLE\_BACKUP\_SUFFIX. The version

control method may be selected via the --backup option or through the VERSION\_CONTROL en?

vironment variable. Here are the values:

none, off

never make backups (even if --backup is given)

numbered, t

make numbered backups

#### existing, nil

numbered if numbered backups exist, simple otherwise

simple, never

always make simple backups

#### AUTHOR

Written by Mike Parker, David MacKenzie, and Jim Meyering.

# REPORTING BUGS

GNU coreutils online help: <https://www.gnu.org/software/coreutils/>

Report any translation bugs to <https://translationproject.org/team/>

### COPYRIGHT

Copyright ? 2020 Free Software Foundation, Inc. License GPLv3+: GNU GPL version 3 or

later <https://gnu.org/licenses/gpl.html>.

This is free software: you are free to change and redistribute it. There is NO WARRANTY,

to the extent permitted by law.

## SEE ALSO

rename(2)

Full documentation <https://www.gnu.org/software/coreutils/mv>

or available locally via: info '(coreutils) mv invocation'

GNU coreutils 8.32 February 2024 MV(1)