

Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'needrestart.1'

\$ man needrestart.1

NEEDRESTART(1)

User Commands

NEEDRESTART(1)

NAME

needrestart - needrestart

DESCRIPTION

needrestart checks which daemons need to be restarted after library upgrades.

USAGE

Usage:

needrestart [-(v|q)] [-n] [-c <cfg>] [-r <mode>] [-f <fe>] [-u <ui>] [-(b|p)] [-kl]

- -v be more verbose
- -q be quiet
- -m <mode>

set level of technical details

- e (e)asy mode
- a (a)dvanced mode
- -n set default answer to 'no'
- -c <cfg>

config filename

-r <mode>

set restart mode

- I (I)ist only
- i (i)nteractive restart
- a (a)utomatically restart

ATTENTION: If needrestart is configured to run in interactive mode but is run non-

interactive (i.e. unattended-upgrades) it will fallback to list only mode.

-b enable batch mode

-p nagios plugin mode: makes output and exit codes nagios compatible

-f <fe>

override debconf(7) frontend, sets the DEBIAN_FRONTEND environment variable to <fe>-t <seconds>

When checking running interpreter processes, allow process start times that are close to timestamps of files the interpreter uses, within this tolerance (default 2). The default value of 2 seconds is best for checks of Linux hosts, on which sys? tem limitations prevent more accurate measurements of process start times. Values higher than 0 should prevent false positives yet may in extreme cases cause false negatives; values higher than 2 should not be necessary.

-u <ui>

use preferred UI package (-u ? shows available packages)

By using one of the following options only the specified checks are performed:

- -k check for obsolete kernel
- -l check for obsolete libraries

ENVIRONMENT

The following environment variables can be used to override the config file options. Com? mand line parameters do always supersede them.

NEEDRESTART_MODE

Change the configured restart mode (see also the -r parameter): (I)ist only,

(i)nteractive or (a)utomatically

When used with apt-get(8) needrestart supports the following additional environment vari? ables:

DEBIAN_FRONTEND

The debconf(7) frontend to use, can also set using the -f parameter.

NEEDRESTART_SUSPEND

If set to a non-empty value the apt-get(8) hook will not run needrestart after in?

stalling or updating packages.

AUTHOR

Thomas Liske <thomas@fiasko-nw.net>

COPYRIGHT

2013 - 2020 (C) Thomas Liske [http://fiasko-nw.net/~thomas/]

This program is free software; you can redistribute it and/or modify it under the terms of

the GNU General Public License as published by the Free Software Foundation; either ver?

sion 2 of the License, or (at your option) any later version.

UPSTREAM

https://github.com/liske/needrestart

needrestart

January 2015

NEEDRESTART(1)