

# Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

## Rocky Enterprise Linux 9.2 Manual Pages on command 'pptpsetup.8'

## \$ man pptpsetup.8

PPTPSETUP(8)

User Contributed Perl Documentation

PPTPSETUP(8)

## NAME

pptpsetup - Point-to-Point Tunneling Protocol setup

## SYNOPSIS

pptpsetup --create <TUNNEL> --server <SERVER> [--domain <DOMAIN>]

--username <USERNAME> [--password <PASSWORD>]

[--encrypt] [--start]

pptpsetup --delete <TUNNEL>

## DESCRIPTION

PPTP Client is a Linux, FreeBSD, NetBSD and OpenBSD client for the proprietary Microsoft

Point-to-Point Tunneling Protocol, PPTP.

This script configures PPTP Client on Linux.

## OPTIONS

--create TUNNEL create a tunnel named TUNNEL

--delete TUNNEL delete the file /etc/ppp/peers/TUNNEL and any lines from

/etc/ppp/chap-secrets that contains "TUNNEL" as a single word

--server SERVER the IP address or host name of the server

--domain DOMAIN the authentication domain name (optional)

#### --username USERNAME

the username you are to use

#### --password PASSWORD

the password you are to use. If you don't specify a password, pptpsetup will ask for one.

--encrypt whether encryption is required

--start whether the connection should be started after configuration.

#### AUTHOR

Nelson Ferraz <nferraz at gmail.com>, based on James Cameron's PPTP Client Debian HOWTO.

#### SEE ALSO

PPTP Client Debian HOWTO

http://pptpclient.sourceforge.net/howto-debian.phtml

## PPTP Client Diagnosis HOWTO

http://pptpclient.sourceforge.net/howto-diagnosis.phtml

#### COPYRIGHT

pptpsetup - Point-to-Point Tunneling Protocol setup

Copyright (C) 2006 Nelson Ferraz

This program is free software; you can redistribute it and/or modify it under the terms of

the GNU General Public License as published by the Free Software Foundation; either

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 51 Franklin St, Fifth Floor, Boston, MA 02110-1301 USA

perl v5.34.0

2022-03-24

PPTPSETUP(8)