



### ***Linux Ubuntu 22.4.5 Manual Pages on command 'virkeycode-atset1.7'***

***\$ man virkeycode-atset1.7***

VIRKEYCODE-ATSET1(7)      Virtualization Support      VIRKEYCODE-ATSET1(7)

#### NAME

virkeycode-atset1 - Key code values for atset1

#### DESCRIPTION

List of atset1 key code values, with corresponding linux key code names

? 1 (0x1)

Key name KEY\_ESC

? 2 (0x2)

Key name KEY\_1

? 3 (0x3)

Key name KEY\_2

? 4 (0x4)

Key name KEY\_3

? 5 (0x5)

Key name KEY\_4

? 6 (0x6)

Key name KEY\_5

? 7 (0x7)

Key name KEY\_6

? 8 (0x8)

Key name KEY\_7

? 9 (0x9)

Key name KEY\_8

? 10 (0xa)

Key name KEY\_9

? 11 (0xb)

Key name KEY\_0

? 12 (0xc)

Key name KEY\_MINUS

? 13 (0xd)

Key name KEY\_EQUAL

? 14 (0xe)

Key name KEY\_BACKSPACE

? 15 (0xf)

Key name KEY\_TAB

? 16 (0x10)

Key name KEY\_Q

? 17 (0x11)

Key name KEY\_W

? 18 (0x12)

Key name KEY\_E

? 19 (0x13)

Key name KEY\_R

? 20 (0x14)

Key name KEY\_T

? 21 (0x15)

Key name KEY\_Y

? 22 (0x16)

Key name KEY\_U

? 23 (0x17)

Key name KEY\_I

? 24 (0x18)

Key name KEY\_O

? 25 (0x19)

Key name KEY\_P

? 26 (0x1a)

Key name KEY\_LEFTBRACE

? 27 (0x1b)

Key name KEY\_RIGHTBRACE

? 28 (0x1c)

Key name KEY\_ENTER

? 29 (0x1d)

Key name KEY\_LEFTCTRL

? 30 (0x1e)

Key name KEY\_A

? 31 (0x1f)

Key name KEY\_S

? 32 (0x20)

Key name KEY\_D

? 33 (0x21)

Key name KEY\_F

? 34 (0x22)

Key name KEY\_G

? 35 (0x23)

Key name KEY\_H

? 36 (0x24)

Key name KEY\_J

? 37 (0x25)

Key name KEY\_K

? 38 (0x26)

Key name KEY\_L

? 39 (0x27)

Key name KEY\_SEMICOLON

? 40 (0x28)

Key name KEY\_APOSTROPHE

? 41 (0x29)

Key name KEY\_GRAVE

? 42 (0x2a)

Key name KEY\_LEFTSHIFT

? 43 (0x2b)

Key name KEY\_BACKSLASH

? 44 (0x2c)

Key name KEY\_Z

? 45 (0x2d)

Key name KEY\_X

? 46 (0x2e)

Key name KEY\_C

? 47 (0x2f)

Key name KEY\_V

? 48 (0x30)

Key name KEY\_B

? 49 (0x31)

Key name KEY\_N

? 50 (0x32)

Key name KEY\_M

? 51 (0x33)

Key name KEY\_COMMA

? 52 (0x34)

Key name KEY\_DOT

? 53 (0x35)

Key name KEY\_SLASH

? 54 (0x36)

Key name KEY\_RIGHTSHIFT

? 55 (0x37)

Key name KEY\_KPASTERISK

? 56 (0x38)

Key name KEY\_LEFTALT

? 57 (0x39)

Key name KEY\_SPACE

? 58 (0x3a)

Key name KEY\_CAPSLOCK

? 59 (0x3b)

Key name KEY\_F1

? 60 (0x3c)

Key name KEY\_F2

? 61 (0x3d)

Key name KEY\_F3

? 62 (0x3e)



Key name KEY\_F4

? 63 (0x3f)

Key name KEY\_F5

? 64 (0x40)

Key name KEY\_F6

? 65 (0x41)

Key name KEY\_F7

? 66 (0x42)

Key name KEY\_F8

? 67 (0x43)

Key name KEY\_F9

? 68 (0x44)

Key name KEY\_F10

? 69 (0x45)

Key name KEY\_NUMLOCK

? 70 (0x46)

Key name KEY\_SCROLLLOCK

? 71 (0x47)

Key name KEY\_KP7

? 72 (0x48)

Key name KEY\_KP8

? 73 (0x49)

Key name KEY\_KP9

? 74 (0x4a)

Key name KEY\_KPMINUS

? 75 (0x4b)

Key name KEY\_KP4

? 76 (0x4c)

Key name KEY\_KP5

? 77 (0x4d)

Key name KEY\_KP6

? 78 (0x4e)

Key name KEY\_KPPLUS

? 79 (0x4f)

Key name KEY\_KP1

? 80 (0x50)

Key name KEY\_KP2

? 81 (0x51)

Key name KEY\_KP3

? 82 (0x52)

Key name KEY\_KP0

? 83 (0x53)

Key name KEY\_KPDOT

? 84 (0x54)

Key name KEY\_SYSRQ

? 85 (0x55)

Key name KEY\_F16

? 86 (0x56)

Key name KEY\_102ND

? 87 (0x57)

Key name KEY\_F11

? 88 (0x58)

Key name KEY\_F12

? 89 (0x59)

Key name KEY\_KPEQUAL

? 90 (0x5a)

Key name KEY\_F20

? 91 (0x5b)

Key name KEY\_LINEFEED

? 92 (0x5c)

Key name KEY\_KPJPCOMMA

? 93 (0x5d)

Key name KEY\_F13

? 94 (0x5e)

Key name KEY\_F14

? 95 (0x5f)

Key name KEY\_F15

? 99 (0x63)

Key name KEY\_PHONE

? 100 (0x64)

Key name KEY\_OPEN

? 101 (0x65)

Key name KEY\_PASTE

? 102 (0x66)

Key name KEY\_SETUP

? 103 (0x67)

Key name KEY\_FILE

? 104 (0x68)

Key name KEY\_SENDFILE

? 105 (0x69)

Key name KEY\_DELETEFILE

? 106 (0x6a)

Key name KEY\_MSDOS

? 107 (0x6b)

Key name KEY\_DIRECTION

? 108 (0x6c)

Key name KEY\_EJECTCD

? 109 (0x6d)

Key name KEY\_F23

? 111 (0x6f)

Key name KEY\_F24

? 112 (0x70)

Key name KEY\_KATAKANAHIRAGANA

? 113 (0x71)

Key name KEY\_EXIT

? 114 (0x72)

Key name KEY\_MOVE

? 115 (0x73)

Key name KEY\_RO

? 116 (0x74)

Key name KEY\_F21

? 117 (0x75)

Key name KEY\_SCROLLUP

? 118 (0x76)

Key name KEY\_ZENKAKUHANKAKU

? 119 (0x77)

Key name KEY\_HIRAGANA

? 120 (0x78)

Key name KEY\_KATAKANA

? 121 (0x79)

Key name KEY\_HENKAN

? 123 (0x7b)

Key name KEY\_MUHENKAN

? 125 (0x7d)

Key name KEY\_YEN

? 126 (0x7e)

Key name KEY\_KPCOMMA

? 57345 (0xe001)

Key name KEY\_CONFIG

? 57346 (0xe002)

Key name KEY\_WWW

? 57347 (0xe003)

Key name KEY\_F17

? 57348 (0xe004)

Key name KEY\_F19

? 57349 (0xe005)

Key name KEY\_AGAIN

? 57350 (0xe006)

Key name KEY\_PROPS

? 57351 (0xe007)

Key name KEY\_UNDO

? 57352 (0xe008)



Key name KEY\_EDIT

? 57353 (0xe009)

Key name KEY\_NEW

? 57354 (0xe00a)

Key name KEY\_REDO

? 57355 (0xe00b)

Key name KEY\_SCALE

? 57356 (0xe00c)

Key name KEY\_FRONT

? 57357 (0xe00d)

Key name KEY\_HANJA

? 57358 (0xe00e)

Key name KEY\_FORWARDMAIL

? 57359 (0xe00f)

Key name KEY\_SCROLLDOWN

? 57360 (0xe010)

Key name KEY\_PREVIOUSSONG

? 57362 (0xe012)

Key name KEY\_SCREENLOCK

? 57363 (0xe013)

Key name KEY\_XFER

? 57364 (0xe014)

Key name KEY\_ALTERASE

? 57365 (0xe015)

Key name unnamed

? 57366 (0xe016)

Key name unnamed

? 57367 (0xe017)

Key name KEY\_PROG2

? 57368 (0xe018)

Key name KEY\_REWIND

? 57369 (0xe019)

Key name KEY\_NEXTSONG

? 57370 (0xe01a)

Key name unnamed

? 57371 (0xe01b)

Key name unnamed

? 57372 (0xe01c)

Key name KEY\_KPENTER

? 57373 (0xe01d)

Key name KEY\_RIGHTCTRL

? 57374 (0xe01e)

Key name KEY\_MENU

? 57375 (0xe01f)

Key name KEY\_PROG1

? 57376 (0xe020)

Key name KEY\_MUTE

? 57377 (0xe021)

Key name KEY\_CALC

? 57378 (0xe022)

Key name KEY\_PLAYPAUSE

? 57379 (0xe023)

Key name KEY\_CLOSECD

? 57380 (0xe024)

Key name KEY\_STOPCD

? 57381 (0xe025)

Key name KEY\_SUSPEND

? 57382 (0xe026)

Key name KEY\_CYCLEWINDOWS

? 57383 (0xe027)

Key name unnamed

? 57384 (0xe028)

Key name KEY\_PLAYCD

? 57385 (0xe029)

Key name KEY\_PAUSECD

? 57387 (0xe02b)

Key name KEY\_PROG3

? 57388 (0xe02c)

Key name KEY\_PROG4

? 57389 (0xe02d)

Key name KEY\_DASHBOARD

? 57390 (0xe02e)

Key name KEY\_VOLUMEDOWN

? 57391 (0xe02f)

Key name KEY\_CLOSE

? 57392 (0xe030)

Key name KEY\_VOLUMEUP

? 57393 (0xe031)

Key name KEY\_RECORD

? 57394 (0xe032)

Key name KEY\_HOMEPAGE

? 57395 (0xe033)

Key name KEY\_PLAY

? 57396 (0xe034)

Key name KEY\_FASTFORWARD

? 57397 (0xe035)

Key name KEY\_KPSLASH

? 57398 (0xe036)

Key name KEY\_BASSBOOST

? 57400 (0xe038)

Key name KEY\_RIGHTALT

? 57401 (0xe039)

Key name KEY\_PRINT

? 57402 (0xe03a)

Key name KEY\_HP

? 57403 (0xe03b)

Key name KEY\_CAMERA

? 57404 (0xe03c)

Key name KEY\_CUT

? 57405 (0xe03d)

Key name KEY\_SOUND

? 57406 (0xe03e)

Key name KEY\_QUESTION

? 57407 (0xe03f)

Key name KEY\_EMAIL

? 57408 (0xe040)

Key name KEY\_CHAT

? 57409 (0xe041)

Key name KEY\_FIND

? 57410 (0xe042)

Key name KEY\_CONNECT

? 57411 (0xe043)

Key name KEY\_FINANCE

? 57412 (0xe044)

Key name KEY\_SPORT

? 57413 (0xe045)

Key name KEY\_SHOP

? 57414 (0xe046)

Key name KEY\_PAUSE

? 57415 (0xe047)

Key name KEY\_HOME

? 57416 (0xe048)

Key name KEY\_UP

? 57417 (0xe049)

Key name KEY\_PAGEUP

? 57418 (0xe04a)

Key name KEY\_CANCEL

? 57419 (0xe04b)

Key name KEY\_LEFT

? 57420 (0xe04c)

Key name KEY\_BRIGHTNESSDOWN

? 57421 (0xe04d)



Key name KEY\_RIGHT

? 57422 (0xe04e)

Key name KEY\_KPPLUSMINUS

? 57423 (0xe04f)

Key name KEY\_END

? 57424 (0xe050)

Key name KEY\_DOWN

? 57425 (0xe051)

Key name KEY\_PAGEDOWN

? 57426 (0xe052)

Key name KEY\_INSERT

? 57427 (0xe053)

Key name KEY\_DELETE

? 57428 (0xe054)

Key name KEY\_BRIGHTNESSUP

? 57429 (0xe055)

Key name KEY\_SAVE

? 57430 (0xe056)

Key name KEY\_SWITCHVIDEOMODE

? 57431 (0xe057)

Key name KEY\_KBDILLUMTOGGLE

? 57432 (0xe058)

Key name KEY\_KBDILLUMDOWN

? 57433 (0xe059)

Key name KEY\_KBDILLUMUP

? 57434 (0xe05a)

Key name KEY\_SEND

? 57435 (0xe05b)

Key name KEY\_LEFTMETA

? 57436 (0xe05c)

Key name KEY\_RIGHTMETA

? 57437 (0xe05d)

Key name KEY\_COMPOSE

? 57438 (0xe05e)

Key name KEY\_POWER

? 57439 (0xe05f)

Key name KEY\_SLEEP

? 57443 (0xe063)

Key name KEY\_WAKEUP

? 57444 (0xe064)

Key name KEY\_REPLY

? 57445 (0xe065)

Key name KEY\_SEARCH

? 57446 (0xe066)

Key name KEY\_BOOKMARKS

? 57447 (0xe067)

Key name KEY\_REFRESH

? 57448 (0xe068)

Key name KEY\_STOP

? 57449 (0xe069)

Key name KEY\_FORWARD

? 57450 (0xe06a)

Key name KEY\_BACK

? 57451 (0xe06b)

Key name KEY\_COMPUTER

? 57452 (0xe06c)

Key name KEY\_MAIL

? 57453 (0xe06d)

Key name KEY\_MEDIA

? 57455 (0xe06f)

Key name KEY\_MACRO

? 57456 (0xe070)

Key name KEY\_DOCUMENTS

? 57457 (0xe071)

Key name KEY\_BATTERY

? 57458 (0xe072)

Key name KEY\_BLUETOOTH

? 57459 (0xe073)

Key name KEY\_WLAN

? 57460 (0xe074)

Key name KEY\_UWB

? 57461 (0xe075)

Key name KEY\_HELP

? 57462 (0xe076)

Key name KEY\_KPLEFTPAREN

? 57463 (0xe077)

Key name KEY\_F18

? 57464 (0xe078)

Key name KEY\_COPY

? 57465 (0xe079)

Key name KEY\_F22

? 57467 (0xe07b)

Key name KEY\_KPRIGHTPAREN

? 57469 (0xe07d)

Key name KEY\_EJECTCLOSECD

VIRKEYCODE-ATSET1(7)