



Linux Ubuntu 22.4.5 Manual Pages on command 'virkeycode-win32.7'

\$ man virkeycode-win32.7

VIRKEYCODE-WIN32(7) Virtualization Support VIRKEYCODE-WIN32(7)

NAME

virkeycode-win32 - Key code values for win32

DESCRIPTION

List of win32 key code values, with corresponding win32 key code names

? 1 (0x1)

Key name VK_LBUTTON

? 2 (0x2)

Key name VK_RBUTTON

? 4 (0x4)

Key name VK_MBUTTON

? 5 (0x5)

Key name VK_XBUTTON1

? 6 (0x6)

Key name VK_XBUTTON2

? 8 (0x8)

Key name VK_BACK

? 9 (0x9)

Key name VK_TAB

? 13 (0xd)

Key name VK_RETURN

? 16 (0x10)

Key name VK_LSHIFT

? 17 (0x11)

Key name VK_CONTROL

? 18 (0x12)

Key name VK_MENU

? 19 (0x13)

Key name VK_PAUSE

? 20 (0x14)

Key name VK_CAPITAL

? 21 (0x15)

Key name VK_HANGEUL

? 25 (0x19)

Key name VK_HANJA

? 27 (0x1b)

Key name VK_ESCAPE

? 32 (0x20)

Key name VK_SPACE

? 33 (0x21)

Key name VK_PRIOR

? 34 (0x22)

Key name VK_NEXT

? 35 (0x23)

Key name VK_END

? 36 (0x24)

Key name VK_HOME

? 37 (0x25)

Key name VK_LEFT

? 38 (0x26)

Key name VK_UP

? 39 (0x27)

Key name VK_RIGHT

? 40 (0x28)

Key name VK_DOWN

? 41 (0x29)

Key name VK_SELECT

? 42 (0x2a)

Key name VK_PRINT

? 44 (0x2c)

Key name VK_SNAPSHOT

? 45 (0x2d)

Key name VK_INSERT

? 46 (0x2e)

Key name VK_DELETE

? 47 (0x2f)

Key name VK_HELP

? 48 (0x30)

Key name VK_0

? 49 (0x31)

Key name VK_1

? 50 (0x32)

Key name VK_2

? 51 (0x33)

Key name VK_3

? 52 (0x34)

Key name VK_4

? 53 (0x35)

Key name VK_5

? 54 (0x36)

Key name VK_6

? 55 (0x37)

Key name VK_7

? 56 (0x38)

Key name VK_8

? 57 (0x39)

Key name VK_9

? 65 (0x41)

Key name VK_A

? 66 (0x42)

Key name VK_B

? 67 (0x43)

Key name VK_C

? 68 (0x44)

Key name VK_D

? 69 (0x45)

Key name VK_E

? 70 (0x46)

Key name VK_F

? 71 (0x47)

Key name VK_G

? 72 (0x48)

Key name VK_H

? 73 (0x49)

Key name VK_I

? 74 (0x4a)

Key name VK_J

? 75 (0x4b)

Key name VK_K

? 76 (0x4c)

Key name VK_L

? 77 (0x4d)

Key name VK_M

? 78 (0x4e)

Key name VK_N

? 79 (0x4f)

Key name VK_O

? 80 (0x50)

Key name VK_P

? 81 (0x51)

Key name VK_Q

? 82 (0x52)

Key name VK_R

? 83 (0x53)

Key name VK_S

? 84 (0x54)

Key name VK_T

? 85 (0x55)

Key name VK_U

? 86 (0x56)

Key name VK_V

? 87 (0x57)

Key name VK_W

? 88 (0x58)

Key name VK_X

? 89 (0x59)

Key name VK_Y

? 90 (0x5a)

Key name VK_Z

? 91 (0x5b)

Key name VK_LWIN

? 92 (0x5c)

Key name VK_RWIN

? 93 (0x5d)

Key name VK_APPS

? 95 (0x5f)

Key name VK_SLEEP

? 96 (0x60)

Key name VK_NUMPAD0

? 97 (0x61)

Key name VK_NUMPAD1

? 98 (0x62)

Key name VK_NUMPAD2

? 99 (0x63)

Key name VK_NUMPAD3

? 100 (0x64)

Key name VK_NUMPAD4

? 101 (0x65)

Key name VK_NUMPAD5

? 102 (0x66)

Key name VK_NUMPAD6

? 103 (0x67)

Key name VK_NUMPAD7

? 104 (0x68)

Key name VK_NUMPAD8

? 105 (0x69)

Key name VK_NUMPAD9

? 106 (0x6a)

Key name VK_MULTIPLY

? 107 (0x6b)

Key name VK_ADD

? 108 (0x6c)

Key name VK_SEPARATOR??

? 109 (0x6d)

Key name VK_SUBTRACT

? 110 (0x6e)

Key name VK_DECIMAL

? 111 (0x6f)

Key name VK_DIVIDE

? 112 (0x70)

Key name VK_F1

? 113 (0x71)

Key name VK_F2

? 114 (0x72)

Key name VK_F3

? 115 (0x73)

Key name VK_F4

? 116 (0x74)

Key name VK_F5

? 117 (0x75)

Key name VK_F6

? 118 (0x76)

Key name VK_F7

? 119 (0x77)

Key name VK_F8

? 120 (0x78)

Key name VK_F9

? 121 (0x79)

Key name VK_F10

? 122 (0x7a)

Key name VK_F11

? 123 (0x7b)

Key name VK_F12

? 124 (0x7c)

Key name VK_F13

? 125 (0x7d)

Key name VK_F14

? 126 (0x7e)

Key name VK_F15

? 127 (0x7f)

Key name VK_F16

? 128 (0x80)

Key name VK_F17

? 129 (0x81)

Key name VK_F18

? 130 (0x82)

Key name VK_F19

? 131 (0x83)

Key name VK_F20

? 132 (0x84)

Key name VK_F21

? 133 (0x85)

Key name VK_F22

? 134 (0x86)

Key name VK_F23

? 135 (0x87)

Key name VK_F24

? 144 (0x90)

Key name VK_NUMLOCK

? 145 (0x91)

Key name VK_SCROLL

? 160 (0xa0)

Key name VK_LSHIFT

? 161 (0xa1)

Key name VK_RSHIFT

? 162 (0xa2)

Key name VK_CONTROL

? 163 (0xa3)

Key name VK_RCONTROL

? 164 (0xa4)

Key name VK_MENU

? 165 (0xa5)

Key name VK_RMENU

? 166 (0xa6)

Key name VK_BROWSER_BACK

? 167 (0xa7)

Key name VK_BROWSER_FORWARD

? 168 (0xa8)

Key name VK_BROWSER_REFRESH

? 169 (0xa9)

Key name VK_BROWSER_STOP

? 170 (0xaa)

Key name VK_BROWSER_SEARCH

? 171 (0xab)

Key name VK_BROWSER_FAVOURITES

? 172 (0xac)

Key name VK_BROWSER_HOME

? 173 (0xad)

Key name VK_VOLUME_MUTE

? 174 (0xae)

Key name VK_VOLUME_DOWN

? 175 (0xaf)

Key name VK_VOLUME_UP

? 176 (0xb0)

Key name VK_MEDIA_NEXT_TRACK

? 177 (0xb1)

Key name VK_MEDIA_PREV_TRACK

? 178 (0xb2)

Key name VK_MEDIA_STOP

? 179 (0xb3)

Key name VK_MEDIA_PLAY_PAUSE

? 180 (0xb4)

Key name VK_LAUNCH_MAIL

? 186 (0xba)

Key name VK_OEM_1

? 187 (0xbb)

Key name VK_OEM_PLUS

? 188 (0xbc)

Key name VK_OEM_COMMA

? 189 (0xbd)

Key name VK_OEM_MINUS

? 190 (0xbe)

Key name VK_OEM_PERIOD

? 191 (0xbf)

Key name VK_OEM_2

? 192 (0xc0)

Key name VK_OEM_3

? 219 (0xdb)

Key name VK_OEM_4

? 220 (0xdc)

Key name VK_OEM_5

? 221 (0xdd)

Key name VK_OEM_6

? 222 (0xde)

Key name VK_OEM_7

? 225 (0xe1)

Key name VK_OEM_102

? 250 (0xfa)

Key name VK_PLAY

? 251 (0xfb)

Key name VK_ZOOM

VIRKEYCODE-WIN32(7)