

Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

## Rocky Enterprise Linux 9.2 Manual Pages on command 'xkbevd.1'

# \$ man xkbevd.1

XKBEVD(1)

General Commands Manual

XKBEVD(1)

NAME

xkbevd - XKB event daemon

**SYNOPSIS** 

xkbevd [ options ]

#### **DESCRIPTION**

This command is very raw and is therefore only partially implemented; we present it here as a rough prototype for developers, not as a general purpose tool for end users. Some? thing like this might make a suitable replacement for xev; I'm not signing up, mind you, but it's an interesting idea.

The xkbevd event daemon listens for specified XKB events and executes requested commands if they occur. The configuration file consists of a list of event specification/action pairs and/or variable definitions.

An event specification consists of a short XKB event name followed by a string or identi? fier which serves as a qualifier in parentheses; empty parenthesis indicate no qualifica? tion and serve to specify the default command which is applied to events which do not match any of the other specifications. The interpretation of the qualifier depends on the type of the event: Bell events match using the name of the bell, message events match on the contents of the message string and slow key events accept any of press, release, ac? cept, or reject. No other events are currently recognized.

An action consists of an optional keyword followed by an optional string argument. Cur? rently, xkbev recognizes the actions: none, ignore, echo, printEvent, sound, and shell.

If the action is not specified, the string is taken as the name of a sound file to be

played unless it begins with an exclamation point, in which case it is taken as a shell command.

Variable definitions in the argument string are expanded with fields from the event in question before the argument string is passed to the action processor. The general syntax for a variable is either \$c or \$(str), where c is a single character and str is a string of arbitrary length. All parameters have both single-character and long names.

The list of recognized parameters varies from event to event and is too long to list here right now. This is a developer release anyway, so you can be expected to look at the source code (evargs.c is of particular interest).

The ignore, echo, printEvent, sound, and shell actions do what you would expect commands named ignore, echo, printEvent, sound, and shell to do, except that the sound command has only been implemented and tested for SGI machines. It launches an external program right now, so it should be pretty easy to adapt, especially if you like audio cues that arrive about a half-second after you expect them.

The only currently recognized variables are soundDirectory and soundCmd. I'm sure you can figure out what they do.

## **OPTIONS**

-help Prints a usage message that is far more up-to-date than anything in this man page.

-cfg file

Specifies the configuration file to read. If no configuration file is specified, xkbevd looks for ~/.xkb/xkbevd.cf and \$(LIBDIR)/xkb/xkbevd.cf in that order.

-sc cmd Specifies the command used to play sounds.

-sd directory

Specifies a top-level directory for sound files.

-display display

Specifies the display to use. If not present, xkbevd uses \$DISPLAY.

- -bg Tells xkbevd to fork itself (and run in the background).
- -synch Forces synchronization of all X requests. Slow.
- Print more information, including debugging messages. Multiple specifications of
   v cause more output, to a point.

## -version

Prints the program version and exits.

SEE ALSO Page 2/3

xev(1), xkbwatch(1), X(7).

COPYRIGHT

Copyright 1995, Silicon Graphics Computer Systems

Copyright 1995, 1998 The Open Group

See X(7) for a full statement of rights and permissions.

**AUTHOR** 

Erik Fortune, Silicon Graphics

X Version 11 xkbevd 1.1.4

XKBEVD(1)