



python



PowerShell

FPDF Library
PDF generator

Full credit is given to the above companies including the OS that this PDF file was generated!

PowerShell Get-Help on command 'Disable-ComputerRestore'

PS C:\Users\wahid> Get-Help Disable-ComputerRestore

NAME

Disable-ComputerRestore

SYNOPSIS

Disables the System Restore feature on the specified file system drive.

SYNTAX

Disable-ComputerRestore [-Drive] <System.String[]> [-Confirm] [-WhatIf]
[<CommonParameters>]

DESCRIPTION

The `Disable-ComputerRestore` cmdlet turns off the System Restore feature on one or more file system drives. As a result, attempts to restore the computer do not affect the specified drive.

To disable System Restore on any drive, it must be disabled on the system drive, either first or concurrently.

To re-enable System Restore, use the Enable-ComputerRestore cmdlet. To find

the state of System Restore for each drive, use `Rstrui.exe`.

System restore points and the ComputerRestore cmdlets are supported only on client operating systems, such as Windows 7, Windows Vista, and Windows XP.

PARAMETERS

`-Drive <System.String[]>`

Specifies the file system drives. Enter one or more file system drive letters, each followed by a colon and a backslash and enclosed in quotation marks, such as C:\ or D:\. This parameter is required.

You cannot use this cmdlet to disable System Restore on a remote network drive, even if the drive is mapped to the local computer, and you cannot disable System Restore on drives that are not eligible for System Restore, such as external drives.

To disable System Restore on any drive, System Restore must be disabled on the system drive, either before or concurrently.

`-Confirm <System.Management.Automation.SwitchParameter>`

Prompts you for confirmation before running the cmdlet.

`-WhatIf <System.Management.Automation.SwitchParameter>`

Shows what would happen if the cmdlet runs. The cmdlet is not run.

`<CommonParameters>`

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see `about_CommonParameters` (<https://go.microsoft.com/fwlink/?LinkID=113216>).

--- Example 1: Disable System Restore on the specified drive ---

```
Disable-ComputerRestore -Drive "C:\"
```

This command disables System Restore on the C: drive.

----- Example 2: Disable System Restore on multiple drives -----

```
Disable-ComputerRestore "C:\", "D:\"
```

This command disables System Restore on the C: and D: drives. The command uses the Drive parameter, but it omits the Drive parameter name.

REMARKS

To see the examples, type: "get-help Disable-ComputerRestore -examples".

For more information, type: "get-help Disable-ComputerRestore -detailed".

For technical information, type: "get-help Disable-ComputerRestore -full".

For online help, type: "get-help Disable-ComputerRestore -online"