



python



PowerShell

FPDF Library
PDF generator

Full credit is given to the above companies including the OS that this PDF file was generated!

PowerShell Get-Help on command 'Enable-BitLockerAutoUnlock'

PS C:\Users\wahid> Get-Help Enable-BitLockerAutoUnlock

NAME

Enable-BitLockerAutoUnlock

SYNOPSIS

Enables automatic unlocking for a BitLocker volume.

SYNTAX

```
Enable-BitLockerAutoUnlock [-MountPoint] <String[]> [-Confirm] [-WhatIf]  
[<CommonParameters>]
```

DESCRIPTION

The Enable-BitLockerAutoUnlock cmdlet enables automatic unlocking for a volume protected by BitLocker Disk Encryption.

You can configure BitLocker to automatically unlock volumes that do not host an operating system. After a user unlocks the operating system volume, BitLocker uses encrypted information stored in the registry and volume metadata to unlock any data volumes that use automatic unlocking.

For an overview of BitLocker, see BitLocker Drive Encryption Overview (<https://technet.microsoft.com/en-us/library/cc732774.aspx>) on TechNet.

PARAMETERS

-Confirm [<SwitchParameter>]

Prompts you for confirmation before running the cmdlet.

-MountPoint <String[]>

Specifies an array of drive letters or BitLocker volume objects. The cmdlet enables automatic unlocking for the volumes specified. To obtain a BitLocker volume object, use the Get-BitLockerVolume cmdlet.

-WhatIf [<SwitchParameter>]

Shows what would happen if the cmdlet runs. The cmdlet is not run.

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

----- Example 1: Enable automatic unlocking -----

```
PS C:\>Enable-BitLockerAutoUnlock -MountPoint "E:"
```

This command enables automatic unlocking for the specified BitLocker volume.

REMARKS

To see the examples, type: "get-help Enable-BitLockerAutoUnlock -examples".

For more information, type: "get-help Enable-BitLockerAutoUnlock -detailed".

For technical information, type: "get-help Enable-BitLockerAutoUnlock -full".

For online help, type: "get-help Enable-BitLockerAutoUnlock -online"

