



python



PowerShell

FPDF Library
PDF generator

Full credit is given to the above companies including the OS that this PDF file was generated!

PowerShell Get-Help on command 'Export-StartLayoutEdgeAssets'

PS C:\Users\wahid> Get-Help Export-StartLayoutEdgeAssets

NAME

Export-StartLayoutEdgeAssets

SYNOPSIS

Exports secondary tiles for Microsoft Edge that display a custom image.

SYNTAX

```
Export-StartLayoutEdgeAssets -LiteralPath <String> [-Confirm] [-WhatIf]  
[<CommonParameters>]
```

```
Export-StartLayoutEdgeAssets [-Path] <String> [-Confirm] [-WhatIf]  
[<CommonParameters>]
```

DESCRIPTION

The Export-StartLayoutEdgeAssets cmdlet exports secondary tiles for Microsoft Edge that display a custom image. Use Export-StartLayout (./Export-StartLayout.md) and [Import-StartLayout](./Import-StartLayout.md) along with the current cmdlet to import the assets. For more information, see Add image for secondary Microsoft

Edge tiles (/windows/configuration/start-secondary-tiles).

The provisioning policies that use the exported assets are no longer used with the Windows 11 Start menu.

PARAMETERS

-LiteralPath <String>

Specifies a literal path for an asset file. Include the `.xml` file name extension. This parameter does not accept the wildcard character (`*`). If the path includes an escape character (`\`), enclose the string in single quotes (`'`).

-Path <String>

Specifies an absolute path for an asset file. Include the `.xml` file name extension. This parameter does not accept the wildcard character (`*`).

-Confirm [<SwitchParameter>]

Prompts you for confirmation before running the cmdlet.

-WhatIf [<SwitchParameter>]

Shows what would happen if the cmdlet runs. The cmdlet is not run.

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see `about_CommonParameters` (<https://go.microsoft.com/fwlink/?LinkID=113216>).

----- Example 1: Export assets -----

```
Export-StartLayoutEdgeAssets -Path "C:\Layouts\assets.xml"
```

This example exports the assets to the file `assets.xml` in the `C:\Layouts` folder. This cmdlet doesn't append `.xml` to a file name.

REMARKS

To see the examples, type: "get-help Export-StartLayoutEdgeAssets -examples".

For more information, type: "get-help Export-StartLayoutEdgeAssets -detailed".

For technical information, type: "get-help Export-StartLayoutEdgeAssets -full".

For online help, type: "get-help Export-StartLayoutEdgeAssets -online"