



python



PowerShell

FPDF Library
PDF generator

Full credit is given to the above companies including the OS that this PDF file was generated!

PowerShell Get-Help on command 'Get-AutologgerConfig'

PS C:\Users\wahid> Get-Help Get-AutologgerConfig

NAME

Get-AutologgerConfig

SYNOPSIS

Enumerates existing AutoLogger session configurations.

SYNTAX

```
Get-AutologgerConfig [[-Name] <String[]>] [-AsJob] [-CimSession  
<CimSession[]>] [-ThrottleLimit <Int32>] [<CommonParameters>]
```

DESCRIPTION

The Get-AutologgerConfig cmdlet enumerates existing AutoLogger session configurations.

PARAMETERS

-AsJob [<SwitchParameter>]

Runs the cmdlet as a background job. Use this parameter to run commands that take a long time to complete.

The cmdlet immediately returns an object that represents the job and then displays the command prompt. You can continue to work in the session while the job completes. To manage the job, use the ``*-Job`` cmdlets. To get the job results, use the `Receive-Job` (<https://go.microsoft.com/fwlink/?LinkID=113372>) cmdlet.

For more information about Windows PowerShell background jobs, see `about_Jobs` (<https://go.microsoft.com/fwlink/?LinkID=113251>).

`-CimSession <CimSession[]>`

Runs the cmdlet in a remote session or on a remote computer. Enter a computer name or a session object, such as the output of a `New-CimSession` (<https://go.microsoft.com/fwlink/p/?LinkId=227967>) or `[Get-CimSession]` (<https://go.microsoft.com/fwlink/p/?LinkId=227966>) cmdlet. The default is the current session on the local computer.

`-Name <String[]>`

Specifies the name of the AutoLogger session.

`-ThrottleLimit <Int32>`

Specifies the maximum number of concurrent operations that can be established to run the cmdlet. If this parameter is omitted or a value of ``0`` is entered, then Windows PowerShell calculates an optimum throttle limit for the cmdlet based on the number of CIM cmdlets that are running on the computer. The throttle limit applies only to the current cmdlet, not to the session or to the computer.

`<CommonParameters>`

This cmdlet supports the common parameters: `Verbose`, `Debug`, `ErrorAction`, `ErrorVariable`, `WarningAction`, `WarningVariable`, `OutBuffer`, `PipelineVariable`, and `OutVariable`. For more information, see `about_CommonParameters` (<https://go.microsoft.com/fwlink/?LinkID=113216>).

----- Example 1: Get a configuration -----

```
PS C:\> Get-AutologgerConfig -Name "WFP-IPsec Trace"
```

```
Name           : WFP-IPsec Trace
BufferSize     :
ClockType      : 2
DisableRealtimePersistence :
FileCount      :
FileName       : %SystemRoot%\System32\LogFiles\WMI\wfp.etl
FileMax        :
FlushTimer     :
Guid           : {0762bd13-14d5-4928-9db0-6c4e96312988}
LogFileMode    : 0x1202
MaximumFileSize : 8
MaximumBuffers :
MinimumBuffers :
Start          : 0
InitStatus     : 0
```

This command gets the AutoLogger configuration named WFP-IPsec Trace.

REMARKS

To see the examples, type: "get-help Get-AutologgerConfig -examples".

For more information, type: "get-help Get-AutologgerConfig -detailed".

For technical information, type: "get-help Get-AutologgerConfig -full".

For online help, type: "get-help Get-AutologgerConfig -online"