



### ***Windows PowerShell Get-Help on Cmdlet 'Get-AzVMDscExtensionStatus'***

***PS:\>Get-HELP Get-AzVMDscExtensionStatus -Full***

#### NAME

Get-AzVMDscExtensionStatus

#### SYNOPSIS

Gets the status of the DSC extension handler for a virtual machine.

#### SYNTAX

```
Get-AzVMDscExtensionStatus [-ResourceGroupName] <System.String> [-VMName] <System.String> [[-Name]
<System.String>] [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[<CommonParameters>]
```

```
Get-AzVMDscExtensionStatus [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-VM
    <Microsoft.Azure.Commands.Compute.Models.PSVirtualMachine>] [<CommonParameters>]
```

#### DESCRIPTION

The Get-AzVMDscExtensionStatus cmdlet gets the status of the Desired State Configuration (DSC) extension handler for

a virtual machine in a resource group. When a

configuration is applied this cmdlet produces output consistent with the Start-DscConfiguration cmdlet.

## PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

Specifies the name of the Azure Resource Manager resource that represents the extension. The Set-AzVMDscExtension cmdlet sets this name to

Microsoft.Powershell.DSC, which is the same value that is used by Get-AzVMDscExtensionStatus . Specify this parameter only if you changed the default name in the

Set cmdlet or used a different resource name in a Resource Manager template.

Required? false

Position? 2

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceGroupName <System.String>

Specifies the name of the resource group of the virtual machine.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-VM <Microsoft.Azure.Commands.Compute.Models.PSVirtualMachine>

Specifies the virtual machine object the extension is on.

Required? false

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-VMName <System.String>

Specifies the name of a virtual machine for which this cmdlet gets the DSC extension status.

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about\\_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

## INPUTS

System.String

## OUTPUTS

## NOTES

----- Example 1 -----

```
Get-AzVMDscExtensionStatus -Name 'AgentPool01' -ResourceGroupName myresourcegroup -VMName 'VM01'
```

## RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.compute/get-azvmdscextensionstatus>

Set-AzVMDscExtension