



python



PowerShell

FPDF Library  
PDF generator

*Full credit is given to the above companies including the OS that this PDF file was generated!*

**PowerShell Get-Help on command 'Get-DnsClientGlobalSetting'**

**PS C:\Users\wahid> Get-Help Get-DnsClientGlobalSetting**

#### NAME

Get-DnsClientGlobalSetting

#### SYNOPSIS

Retrieves global DNS client settings like the suffix search list.

#### SYNTAX

```
Get-DnsClientGlobalSetting [-AsJob] [-CimSession <CimSession[]>]
[-ThrottleLimit <Int32>] [<CommonParameters>]
```

#### DESCRIPTION

The Get-DnsClientGlobalSetting cmdlet retrieves DNS client settings that are global, that are not associated with a specific interface. The settings affect the behavior of the DNS client across all of the interfaces.

#### PARAMETERS

**-AsJob [ <SwitchParameter> ]**

Runs the cmdlet as a background job. Use this parameter to run commands

that take a long time to complete.

The cmdlet immediately returns an object that represents the job and then displays the command prompt. You can continue to work in the session while the job completes. To manage the job, use the `\*-Job` cmdlets. To get the job results, use the Receive-Job  
(<https://go.microsoft.com/fwlink/?LinkId=113372>) cmdlet.

For more information about Windows PowerShell background jobs, see [about\\_Jobs](#) (<https://go.microsoft.com/fwlink/?LinkId=113251>).

#### -CimSession <CimSession[]>

Runs the cmdlet in a remote session or on a remote computer. Enter a computer name or a session object, such as the output of a New-CimSession  
(<https://go.microsoft.com/fwlink/?LinkId=227967>) or  
[Get-CimSession] (<https://go.microsoft.com/fwlink/?LinkId=227966>) cmdlet.  
The default is the current session on the local computer.

#### -ThrottleLimit <Int32>

Specifies the maximum number of concurrent operations that can be established to run the cmdlet. If this parameter is omitted or a value of `0` is entered, then Windows PowerShell calculates an optimum throttle limit for the cmdlet based on the number of CIM cmdlets that are running on the computer. The throttle limit applies only to the current cmdlet, not to the session or to the computer.

#### <CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about\\_CommonParameters](#) (<https://go.microsoft.com/fwlink/?LinkId=113216>).

```
PS C:\> Get-DnsClientGlobalSetting  
UseSuffixSearchList : True  
SuffixSearchList   : {corp.contoso.com, na.corp.contoso.com}  
UseDevolution     : True  
DevolutionLevel   : 0
```

This example gets all of the global DNS client settings.

----- Example 2: Get connection-specific suffixes -----

```
PS C:\> $dnsCGSetting = Get-DnsClientGlobalSetting  
PS C:\> $dnsCGSetting.SuffixSearchList  
corp.contoso.com  
na.corp.contoso.com
```

This example gets the connection-specific suffixes. The first item in the list is the primary DNS suffix, if configured.

## REMARKS

To see the examples, type: "get-help Get-DnsClientGlobalSetting -examples".

For more information, type: "get-help Get-DnsClientGlobalSetting -detailed".

For technical information, type: "get-help Get-DnsClientGlobalSetting -full".

For online help, type: "get-help Get-DnsClientGlobalSetting -online"