



## *Windows PowerShell Get-Help on Cmdlet 'Remove-AzADGroupOwner'*

***PS:\>Get-HELP Remove-AzADGroupOwner -Full***

### NAME

Remove-AzADGroupOwner

### SYNOPSIS

Delete ref of navigation property owners for groups

### SYNTAX

```
Remove-AzADGroupOwner -GroupId <String> -OwnerId <String> [-DefaultProfile <PSObject>] [-Break]
[-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend
<SendAsyncStep[]>] [-PassThru] [-Proxy <Uri>] [-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials]
[-WhatIf] [-Confirm] [<CommonParameters>]
```

### DESCRIPTION

Delete ref of navigation property owners for groups

### PARAMETERS

-GroupId <String>

The unique identifier of group

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-OwnerId <String>

The unique identifier of directoryObject

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-PassThru [<SwitchParameter>]

Returns true when the command succeeds

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position?            named

Default value

Accept pipeline input?    false

Accept wildcard characters? false

**-ProxyCredential <PSCredential>**

Credentials for a proxy server to use for the remote call

Required?            false

Position?            named

Default value

Accept pipeline input?    false

Accept wildcard characters? false

**-ProxyUseDefaultCredentials [<SwitchParameter>]**

Use the default credentials for the proxy

Required?            false

Position?            named

Default value            False

Accept pipeline input?    false

Accept wildcard characters? false

**-WhatIf [<SwitchParameter>]**

Required?            false

Position?            named

Default value

Accept pipeline input?    false

Accept wildcard characters? false

**-Confirm [<SwitchParameter>]**

Required? false  
Position? named  
Default value  
Accept pipeline input? false  
Accept wildcard characters? false

#### <CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about\\_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

#### INPUTS

#### OUTPUTS

System.Boolean

#### ----- EXAMPLE 1 -----

```
PS C:\>$groupId = (Get-AzADGroup -DisplayName "someGroup").Id  
  
$ownerId = (Get-AzADGroupOwner -GroupId $groupId)[0].Id  
Remove-AzADGroupOwner -GroupId $groupId -OwnerId $ownerId
```

#### RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.resources/remove-azadgroupowner>

