



python



PowerShell

FPDF Library  
PDF generator

*Full credit is given to the above companies including the OS that this PDF file was generated!*

### ***PowerShell Get-Help on command 'Remove-ProvisioningPackage'***

***PS C:\Users\wahid> Get-Help Remove-ProvisioningPackage***

#### NAME

Uninstall-ProvisioningPackage

#### SYNOPSIS

Uninstalls .PPKG package from the local machine.

#### SYNTAX

Uninstall-ProvisioningPackage -AllInstalledPackages [-ConnectedDevice]  
[-LogsDirectoryPath <String>] [-WprpFile <String>] [<CommonParameters>]

Uninstall-ProvisioningPackage [-PackageId] <String> [-ConnectedDevice]  
[-LogsDirectoryPath <String>] [-WprpFile <String>] [<CommonParameters>]

Uninstall-ProvisioningPackage [-ConnectedDevice] [-LogsDirectoryPath <String>]  
-PackagePath <String> [-WprpFile <String>] [<CommonParameters>]

Uninstall-ProvisioningPackage [-RuntimeMetadata] <RuntimeProvPackageMetadata>  
[-ConnectedDevice] [-LogsDirectoryPath <String>] [-WprpFile <String>]  
[<CommonParameters>]

## DESCRIPTION

Uninstalls .PPKG package based on package ID, path, metadata, or all packages.

The Uninstall-ProvisioningPackage cmdlet is supported on Windows 11 client operating system only.

## PARAMETERS

-AllInstalledPackages [<SwitchParameter>]

Removes all installed packages.

-ConnectedDevice [<SwitchParameter>]

If enabled, specifies that the device type is mobile.

-LogsDirectoryPath <String>

Specifies the logs directory path.

-PackageId <String>

Specifies the ID of a package.

-PackagePath <String>

Specifies the package path.

-RuntimeMetadata <RuntimeProvPackageMetadata>

Specifies a runtime provisioning package metadata object.

-WprpFile <String>

Specifies the location of the WPR profile file.

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see [about\\_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

----- Example 1: Uninstall all provisioning packages -----

```
PS C:\> Uninstall-ProvisioningPackage -AllInstalledPackages
```

Uninstalls all provisioning packages.

#### REMARKS

To see the examples, type: "get-help Uninstall-ProvisioningPackage -examples".

For more information, type: "get-help Uninstall-ProvisioningPackage -detailed".

For technical information, type: "get-help Uninstall-ProvisioningPackage -full".

For online help, type: "get-help Uninstall-ProvisioningPackage -online"