



python



PowerShell

FPDF Library
PDF generator

Full credit is given to the above companies including the OS that this PDF file was generated!

PowerShell Get-Help on command 'Uninstall-TrustedProvisioningCertificate'

PS C:\Users\wahid> Get-Help Uninstall-TrustedProvisioningCertificate

NAME

Uninstall-TrustedProvisioningCertificate

SYNOPSIS

Removes a previously installed provisioning certificate.

SYNTAX

```
Uninstall-TrustedProvisioningCertificate [-Thumbprint] <String>  
[-ConnectedDevice] [-LogsDirectoryPath <String>] [-WprpFile <String>]  
[<CommonParameters>]
```

DESCRIPTION

Removes a previously installed provisioning certificate.

The Uninstall-TrustedProvisioningCertificate cmdlet is supported on Windows 11 client operating system only.

PARAMETERS

-ConnectedDevice [<SwitchParameter>]

If enabled, specifies that the device type is mobile.

-LogsDirectoryPath <String>

Specifies the logs directory path.

-Thumbprint <String>

Specifies a certificate thumbprint.

-WprpFile <String>

Specifies the location of the WPR profile file.

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

--- Example 1: Uninstall a trusted provisioning certificate ---

```
PS C:\> Uninstall-TrustedProvisioningCertificate -Thumbprint  
fedd995b45e633d4ef30fcbc8f3a48b627e9a28b
```

Uninstall a trusted provisioning certificate with the specified thumbprint.

REMARKS

To see the examples, type: "get-help Uninstall-TrustedProvisioningCertificate -examples".

For more information, type: "get-help Uninstall-TrustedProvisioningCertificate -detailed".

For technical information, type: "get-help Uninstall-TrustedProvisioningCertificate -full".

For online help, type: "get-help Uninstall-TrustedProvisioningCertificate

-online"

