



python



PowerShell

FPDF Library
PDF generator

Full credit is given to the above companies including the OS that this PDF file was generated!

PowerShell Get-Help on command 'Write-DtcTransactionsTraceSession'

PS C:\Users\wahid> Get-Help Write-DtcTransactionsTraceSession

NAME

Write-DtcTransactionsTraceSession

SYNOPSIS

Writes the data from an active DTC transactions trace session into the log file.

SYNTAX

```
Write-DtcTransactionsTraceSession [-AsJob] [-CimSession <CimSession[]>]
[-ThrottleLimit <Int32>] [<CommonParameters>]
```

DESCRIPTION

The Write-DtcTransactionsTraceSession cmdlet writes the data from an active Distributed Transaction Coordinator (DTC) transactions trace session into the log file. If there is no active session, this cmdlet exits.

PARAMETERS

-AsJob [<SwitchParameter>]

Runs the cmdlet as a background job. Use this parameter to run commands that take a long time to complete.

The cmdlet immediately returns an object that represents the job and then displays the command prompt. You can continue to work in the session while the job completes. To manage the job, use the `*-Job` cmdlets. To get the job results, use the `Receive-Job` (<https://go.microsoft.com/fwlink/?LinkId=113372>) cmdlet.

For more information about Windows PowerShell background jobs, see `about_Jobs` (<https://go.microsoft.com/fwlink/?LinkId=113251>).

-CimSession <CimSession[]>

Runs the cmdlet in a remote session or on a remote computer. Enter a computer name or a session object, such as the output of a `New-CimSession` (<https://go.microsoft.com/fwlink/p/?LinkId=227967>) or `[Get-CimSession]` (<https://go.microsoft.com/fwlink/p/?LinkId=227966>) cmdlet. The default is the current session on the local computer.

-ThrottleLimit <Int32>

Specifies the maximum number of concurrent operations that can be established to run the cmdlet. If this parameter is omitted or a value of `0` is entered, then Windows PowerShell calculates an optimum throttle limit for the cmdlet based on the number of CIM cmdlets that are running on the computer. The throttle limit applies only to the current cmdlet, not to the session or to the computer.

<CommonParameters>

This cmdlet supports the common parameters: `Verbose`, `Debug`, `ErrorAction`, `ErrorVariable`, `WarningAction`, `WarningVariable`, `OutBuffer`, `PipelineVariable`, and `OutVariable`. For more information, see `about_CommonParameters` (<https://go.microsoft.com/fwlink/?LinkId=113216>).

Example 1: Write a DTC transaction trace session to a log file

```
PS C:\> Write-DtcTransactionsTraceSession
```

This command writes current DTC transaction traces session information to a log file.

REMARKS

To see the examples, type: "get-help Write-DtcTransactionsTraceSession -examples".

For more information, type: "get-help Write-DtcTransactionsTraceSession -detailed".

For technical information, type: "get-help Write-DtcTransactionsTraceSession -full".

For online help, type: "get-help Write-DtcTransactionsTraceSession -online"