

Full credit is given to the above companies including the OS that this PDF file was generated!

Red Hat Enterprise Linux Release 9.2 Manual Pages on 'ModemManager.8' command

\$ man ModemManager.8

MODEMMANAGER(8)

System Manager's Manual

MODEMMANAGER(8)

NAME

ModemManager - mobile broadband modem management daemon

SYNOPSIS

ModemManager [OPTION...]

DESCRIPTION

ModemManager provides a unified high level API for communicating with

mobile broadband modems, regardless of the protocol used to communicate

with the actual device (Generic AT, vendor-specific AT, QCDM, QMI,

MBIM...).

ModemManager is a DBus-based system daemon and is not meant to be used

directly from the command line.

APPLICATION OPTIONS

--filter-policy=<policy>

Specify which ports are probed and how:

'ALLOWLIST-ONLY'

Only devices or ports explicitly allowlisted with the

'ID_MM_DEVICE_PROCESS' udev tag are probed.

'STRICT'

Only the TTY ports that are heuristically determined to

be very likely to be modem ports are probed. Nay end up

ignoring some devices.

--no-auto-scan

Fully disable udev-based auto-scan looking for devices.

--initial-kernel-events=<filename>

Specify location of the file where the list of initial kernel

events is available. The ModemManager daemon will process this

file on startup.

--debug

Runs ModemManager with "DEBUG" log level and without daemoniz?

ing. This is useful for debugging, as it directs log output to

the controlling terminal in addition to syslog.

-V, --version

Print the ModemManager software version and exit.

-h, --help

Show application options.

LOGGING OPTIONS

--log-level=<level>

Sets how much information ModemManager sends to the log destina?

tion (usually syslog's "daemon" facility). By default, only in?

formational, warning, and error messages are logged. Given level

must be one of "ERR", "WARN", "INFO" or "DEBUG".

--log-file=<filename>

Specify location of the file where ModemManager will dump its

log messages, instead of syslog.

--log-journal

Output log message to the systemd journal.

--log-timestamps

Include absolute timestamps in the log output.

--log-relative-timestamps

Include timestamps, relative to the start time of the daemon, in

the log output.

TEST OPTIONS

--test-session

Run the ModemManager daemon in the Session bus instead of the

System bus.

--test-enable

Enable the Test DBus interface in the daemon.

--test-plugin-dir=[PATH]

Specify an alternate directory where the daemon should look for

vendor plugins.

AUTHOR

Aleksander Morgado <aleksander@aleksander.es>

SEE ALSO

mmcli(1), NetworkManager(8)

5 September 2014 MODEMMANAGER(8)