



Full credit is given to the above companies including the OS that this PDF file was generated!

Red Hat Enterprise Linux Release 9.2 Manual Pages on 'yum-copr.8' command

\$ man yum-copr.8

YUM-COPR(8) dnf-plugins-core YUM-COPR(8)

NAME

yum-copr - redirecting to DNF copr Plugin

Work with Copr & Playground repositories on the local system.

? The `copr` command is used to add or remove Copr repositories to the local system

? The `playground` is used to enable or disable the Playground repository

SYNOPSIS

`dnf copr [enable|disable|remove|list|search] <parameters>`

`dnf playground [enable|disable|upgrade]`

ARGUMENTS (COPR)

`enable name/project [chroot]`

Enable the name/project Copr repository with the optional `ch?` root.

`disable name/project`

Disable the name/project Copr repository.

`remove name/project`

Remove the name/project Copr repository.

`list --installed`

List installed Copr repositories (default).

`list --enabled`

List enabled Copr repositories.

`list --disabled`

List disabled Copr repositories.

`list --available-by-user=name`

List available Copr repositories for a given name.

`search project`

Search for a given project.

`enable hub/name/project`

Enable the name/project Copr repository from the specified Copr hub, Hub is be specified either by its hostname (eg. `copr.fedo?rainfracloud.org`) or by an ID that's defined in a configuration file.

OPTIONS (COPR)

All general DNF options are accepted, see Options in `dnf(8)` for details.

`--hub Copr`

Specify a Copr hub to use. Default is the Fedora Copr: `https://copr.fedorainfracloud.org`.

CONFIGURATION (COPR)

`/etc/dnf/plugins/copr.conf /etc/dnf/plugins/copr.d/`

Configuration file should contain a section for each hub, each section having hostname

(mandatory), protocol (default `https`) and port (default `443`) parameters.:

`[fedora]`

`[fedora]`

`hostname = copr.fedorainfracloud.org`

`protocol = https`

`port = 443`

ARGUMENTS (PLAYGROUND)

`enable` Enable the Playground repository.

`disable`

Disable the Playground repository.

`upgrade`

Upgrade the Playground repository settings (same as `disable` and then `enable`).

OPTIONS (PLAYGROUND)

All general DNF options are accepted, see Options in `dnf(8)` for details.

EXAMPLES

```
copr enable rhsc/perl516 epel-6-x86_64
```

Enable the rhsc/perl516 Copr repository, using the epel-6-x86_64 chroot.

```
copr disable rhsc/perl516
```

Disable the rhsc/perl516 Copr repository

```
copr list --available-by-user=rita
```

List available Copr projects for user rita.

```
copr search tests
```

Search for Copr projects named tests.

AUTHOR

See AUTHORS in your Core DNF Plugins distribution

COPYRIGHT

2023, Red Hat, Licensed under GPLv2+

4.3.0

Mar 15, 2023

YUM-COPR(8)