

Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'nl.1'

\$ man nl.1

NL(1)

User Commands

NL(1)

NAME

nl - number lines of files

SYNOPSIS

nl [OPTION]... [FILE]...

DESCRIPTION

Write each FILE to standard output, with line numbers added.

With no FILE, or when FILE is -, read standard input.

Mandatory arguments to long options are mandatory for short options

too.

-b, --body-numbering=STYLE

use STYLE for numbering body lines

-d, --section-delimiter=CC

use CC for logical page delimiters

-f, --footer-numbering=STYLE

use STYLE for numbering footer lines

-h, --header-numbering=STYLE

use STYLE for numbering header lines

-i, --line-increment=NUMBER

line number increment at each line

-I, --join-blank-lines=NUMBER

group of NUMBER empty lines counted as one

-n, --number-format=FORMAT

insert line numbers according to FORMAT

-p, --no-renumber

do not reset line numbers for each section

-s, --number-separator=STRING

add STRING after (possible) line number

-v, --starting-line-number=NUMBER

first line number for each section

-w, --number-width=NUMBER

use NUMBER columns for line numbers

--help display this help and exit

--version

output version information and exit

Default options are: -bt -d'\:' -fn -hn -i1 -l1 -n'rn' -s<TAB> -v1 -w6

CC are two delimiter characters used to construct logical page delim?

iters; a missing second character implies ':'.

STYLE is one of:

- a number all lines
- t number only nonempty lines
- n number no lines

pBRE number only lines that contain a match for the basic regular ex?

pression, BRE

FORMAT is one of:

- In left justified, no leading zeros
- rn right justified, no leading zeros
- rz right justified, leading zeros

AUTHOR

Written by Scott Bartram and David MacKenzie.

REPORTING BUGS Page 2/3

GNU coreutils online help: https://www.gnu.org/software/coreutils/

Report any translation bugs to https://translationproject.org/team/

COPYRIGHT

Copyright ? 2020 Free Software Foundation, Inc. License GPLv3+: GNU

GPL version 3 or later https://gnu.org/licenses/gpl.html.

This is free software: you are free to change and redistribute it.

There is NO WARRANTY, to the extent permitted by law.

SEE ALSO

Full documentation https://www.gnu.org/software/coreutils/nl or available locally via: info '(coreutils) nl invocation'

GNU coreutils 8.32 January 2023 NL(1)