



Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'virkeycode-atset1.7'

\$ man virkeycode-atset1.7

VIRKEYCODE-ATSET1(7) Virtualization Support VIRKEYCODE-ATSET1(7)

NAME

virkeycode-atset1 - Key code values for atset1

DESCRIPTION

List of atset1 key code values, with corresponding linux key code names

? 1 (0x1)

Key name KEY_ESC

? 2 (0x2)

Key name KEY_1

? 3 (0x3)

Key name KEY_2

? 4 (0x4)

Key name KEY_3

? 5 (0x5)

Key name KEY_4

? 6 (0x6)

Key name KEY_5

? 7 (0x7)

Key name KEY_6

? 8 (0x8)

Key name KEY_7

? 9 (0x9)

Key name KEY_8

? 10 (0xa)

Key name KEY_9

? 11 (0xb)

Key name KEY_0

? 12 (0xc)

Key name KEY_MINUS

? 13 (0xd)

Key name KEY_EQUAL

? 14 (0xe)

Key name KEY_BACKSPACE

? 15 (0xf)

Key name KEY_TAB

? 16 (0x10)

Key name KEY_Q

? 17 (0x11)

Key name KEY_W

? 18 (0x12)

Key name KEY_E

? 19 (0x13)

Key name KEY_R

? 20 (0x14)

Key name KEY_T

? 21 (0x15)

Key name KEY_Y

? 22 (0x16)

Key name KEY_U

? 23 (0x17)

Key name KEY_I

? 24 (0x18)

Key name KEY_O

? 25 (0x19)

Key name KEY_P

? 26 (0x1a)

Key name KEY_LEFTBRACE

? 27 (0x1b)

Key name KEY_RIGHTBRACE

? 28 (0x1c)

Key name KEY_ENTER

? 29 (0x1d)

Key name KEY_LEFTCTRL

? 30 (0x1e)

Key name KEY_A

? 31 (0x1f)

Key name KEY_S

? 32 (0x20)

Key name KEY_D

? 33 (0x21)

Key name KEY_F

? 34 (0x22)

Key name KEY_G

? 35 (0x23)

Key name KEY_H

? 36 (0x24)

Key name KEY_J

? 37 (0x25)

Key name KEY_K

? 38 (0x26)

Key name KEY_L

? 39 (0x27)

Key name KEY_SEMICOLON

? 40 (0x28)

Key name KEY_APOSTROPHE

? 41 (0x29)

Key name KEY_GRAVE

? 42 (0x2a)

Key name KEY_LEFTSHIFT

? 43 (0x2b)

Key name KEY_BACKSLASH

? 44 (0x2c)

Key name KEY_Z

? 45 (0x2d)

Key name KEY_X

? 46 (0x2e)

Key name KEY_C

? 47 (0x2f)

Key name KEY_V

? 48 (0x30)

Key name KEY_B

? 49 (0x31)

Key name KEY_N

? 50 (0x32)

Key name KEY_M

? 51 (0x33)

Key name KEY_COMMA

? 52 (0x34)

Key name KEY_DOT

? 53 (0x35)

Key name KEY_SLASH

? 54 (0x36)

Key name KEY_RIGHTSHIFT

? 55 (0x37)

Key name KEY_KPASTERISK

? 56 (0x38)

Key name KEY_LEFTALT

? 57 (0x39)

Key name KEY_SPACE

? 58 (0x3a)

Key name KEY_CAPSLOCK

? 59 (0x3b)

Key name KEY_F1

? 60 (0x3c)

Key name KEY_F2

? 61 (0x3d)

Key name KEY_F3

? 62 (0x3e)

Key name KEY_F4

? 63 (0x3f)

Key name KEY_F5

? 64 (0x40)

Key name KEY_F6

? 65 (0x41)

Key name KEY_F7

? 66 (0x42)

Key name KEY_F8

? 67 (0x43)

Key name KEY_F9

? 68 (0x44)

Key name KEY_F10

? 69 (0x45)

Key name KEY_NUMLOCK

? 70 (0x46)

Key name KEY_SCROLLLOCK

? 71 (0x47)

Key name KEY_KP7

? 72 (0x48)

Key name KEY_KP8

? 73 (0x49)

Key name KEY_KP9

? 74 (0x4a)

Key name KEY_KPMINUS

? 75 (0x4b)

Key name KEY_KP4

? 76 (0x4c)

Key name KEY_KP5

? 77 (0x4d)

Key name KEY_KP6

? 78 (0x4e)

Key name KEY_KPPLUS

? 79 (0x4f)

Key name KEY_KP1

? 80 (0x50)

Key name KEY_KP2

? 81 (0x51)

Key name KEY_KP3

? 82 (0x52)

Key name KEY_KP0

? 83 (0x53)

Key name KEY_KPDOT

? 84 (0x54)

Key name KEY_SYSRQ

? 85 (0x55)

Key name KEY_F16

? 86 (0x56)

Key name KEY_102ND

? 87 (0x57)

Key name KEY_F11

? 88 (0x58)

Key name KEY_F12

? 89 (0x59)

Key name KEY_KPEQUAL

? 90 (0x5a)

Key name KEY_F20

? 91 (0x5b)

Key name KEY_LINEFEED

? 92 (0x5c)

Key name KEY_KPJPCOMMA

? 93 (0x5d)

Key name KEY_F13

? 94 (0x5e)

Key name KEY_F14

? 95 (0x5f)

Key name KEY_F15

? 99 (0x63)

Key name KEY_PHONE

? 100 (0x64)

Key name KEY_OPEN

? 101 (0x65)

Key name KEY_PASTE

? 102 (0x66)

Key name KEY_SETUP

? 103 (0x67)

Key name KEY_FILE

? 104 (0x68)

Key name KEY_SENDFILE

? 105 (0x69)

Key name KEY_DELETEFILE

? 106 (0x6a)

Key name KEY_MSDOS

? 107 (0x6b)

Key name KEY_DIRECTION

? 108 (0x6c)

Key name KEY_EJECTCD

? 109 (0x6d)

Key name KEY_F23

? 111 (0x6f)

Key name KEY_F24

? 112 (0x70)

Key name KEY_KATAKANAHIRAGANA

? 113 (0x71)

Key name KEY_HANJA

? 114 (0x72)

Key name KEY_HANGEUL

? 115 (0x73)

Key name KEY_RO

? 116 (0x74)

Key name KEY_F21

? 117 (0x75)

Key name KEY_SCROLLUP

? 118 (0x76)

Key name KEY_ZENKAKUHANKAKU

? 119 (0x77)

Key name KEY_HIRAGANA

? 120 (0x78)

Key name KEY_KATAKANA

? 121 (0x79)

Key name KEY_HENKAN

? 123 (0x7b)

Key name KEY_MUHENKAN

? 125 (0x7d)

Key name KEY_YEN

? 126 (0x7e)

Key name KEY_KPCOMMA

? 57345 (0xe001)

Key name KEY_CONFIG

? 57346 (0xe002)

Key name KEY_WWW

? 57347 (0xe003)

Key name KEY_F17

? 57348 (0xe004)

Key name KEY_F19

? 57349 (0xe005)

Key name KEY_AGAIN

? 57350 (0xe006)

Key name KEY_PROPS

? 57351 (0xe007)

Key name KEY_UNDO

? 57352 (0xe008)

Key name KEY_EDIT

? 57353 (0xe009)

Key name KEY_NEW

? 57354 (0xe00a)

Key name KEY_REDO

? 57355 (0xe00b)

Key name KEY_SCALE

? 57356 (0xe00c)

Key name KEY_FRONT

? 57358 (0xe00e)

Key name KEY_FORWARDMAIL

? 57359 (0xe00f)

Key name KEY_SCROLLDOWN

? 57360 (0xe010)

Key name KEY_PREVIOUSSONG

? 57362 (0xe012)

Key name KEY_SCREENLOCK

? 57363 (0xe013)

Key name KEY_XFER

? 57364 (0xe014)

Key name KEY_ALTERASE

? 57365 (0xe015)

Key name unnamed

? 57366 (0xe016)

Key name unnamed

? 57367 (0xe017)

Key name KEY_PROG2

? 57368 (0xe018)

Key name KEY_REWIND

? 57369 (0xe019)

Key name KEY_NEXTSONG

? 57370 (0xe01a)

Key name unnamed

? 57371 (0xe01b)

Key name unnamed

? 57372 (0xe01c)

Key name KEY_KPENTER

? 57373 (0xe01d)

Key name KEY_RIGHTCTRL

? 57374 (0xe01e)

Key name KEY_MENU

? 57375 (0xe01f)

Key name KEY_PROG1

? 57376 (0xe020)

Key name KEY_MUTE

? 57377 (0xe021)

Key name KEY_CALC

? 57378 (0xe022)

Key name KEY_PLAYPAUSE

? 57379 (0xe023)

Key name KEY_CLOSECD

? 57380 (0xe024)

Key name KEY_STOPCD

? 57381 (0xe025)

Key name KEY_SUSPEND

? 57382 (0xe026)

Key name KEY_CYCLEWINDOWS

? 57383 (0xe027)

Key name unnamed

? 57384 (0xe028)

Key name KEY_PLAYCD

? 57385 (0xe029)

Key name KEY_PAUSECD

? 57387 (0xe02b)

Key name KEY_PROG3

? 57388 (0xe02c)

Key name KEY_PROG4

? 57389 (0xe02d)

Key name KEY_DASHBOARD

? 57390 (0xe02e)

Key name KEY_VOLUMEDOWN

? 57391 (0xe02f)

Key name KEY_CLOSE

? 57392 (0xe030)

Key name KEY_VOLUMEUP

? 57393 (0xe031)

Key name KEY_RECORD

? 57394 (0xe032)

Key name KEY_HOMEPAGE

? 57395 (0xe033)

Key name KEY_PLAY

? 57396 (0xe034)

Key name KEY_FASTFORWARD

? 57397 (0xe035)

Key name KEY_KPSLASH

? 57398 (0xe036)

Key name KEY_BASSBOOST

? 57400 (0xe038)

Key name KEY_RIGHTALT

? 57401 (0xe039)

Key name KEY_PRINT

? 57402 (0xe03a)

Key name KEY_HP

? 57403 (0xe03b)

Key name KEY_CAMERA

? 57404 (0xe03c)

Key name KEY_CUT

? 57405 (0xe03d)

Key name KEY_SOUND

? 57406 (0xe03e)

Key name KEY_QUESTION

? 57407 (0xe03f)

Key name KEY_EMAIL

? 57408 (0xe040)

Key name KEY_CHAT

? 57409 (0xe041)

Key name KEY_FIND

? 57410 (0xe042)

Key name KEY_CONNECT

? 57411 (0xe043)

Key name KEY_FINANCE

? 57412 (0xe044)

Key name KEY_SPORT

? 57413 (0xe045)

Key name KEY_SHOP

? 57414 (0xe046)

Key name KEY_PAUSE

? 57415 (0xe047)

Key name KEY_HOME

? 57416 (0xe048)

Key name KEY_UP

? 57417 (0xe049)

Key name KEY_PAGEUP

? 57418 (0xe04a)

Key name KEY_CANCEL

? 57419 (0xe04b)

Key name KEY_LEFT

? 57420 (0xe04c)

Key name KEY_BRIGHTNESSDOWN

? 57421 (0xe04d)

Key name KEY_RIGHT

? 57422 (0xe04e)

Key name KEY_KPPLUSMINUS

? 57423 (0xe04f)

Key name KEY_END

? 57424 (0xe050)

Key name KEY_DOWN

? 57425 (0xe051)

Key name KEY_PAGEDOWN

? 57426 (0xe052)

Key name KEY_INSERT

? 57427 (0xe053)

Key name KEY_DELETE

? 57428 (0xe054)

Key name KEY_BRIGHTNESSUP

? 57429 (0xe055)

Key name KEY_SAVE

? 57430 (0xe056)

Key name KEY_SWITCHVIDEOMODE

? 57431 (0xe057)

Key name KEY_KBDILLUMTOGGLE

? 57432 (0xe058)

Key name KEY_KBDILLUMDOWN

? 57433 (0xe059)

Key name KEY_KBDILLUMUP

? 57434 (0xe05a)

Key name KEY_SEND

? 57435 (0xe05b)

Key name KEY_LEFTMETA

? 57436 (0xe05c)

Key name KEY_RIGHTMETA

? 57437 (0xe05d)

Key name KEY_COMPOSE

? 57438 (0xe05e)

Key name KEY_POWER

? 57439 (0xe05f)

Key name KEY_SLEEP

? 57443 (0xe063)

Key name KEY_WAKEUP

? 57444 (0xe064)

Key name KEY_REPLY

? 57445 (0xe065)

Key name KEY_SEARCH

? 57446 (0xe066)

Key name KEY_BOOKMARKS

? 57447 (0xe067)

Key name KEY_REFRESH

? 57448 (0xe068)

Key name KEY_STOP

? 57449 (0xe069)

Key name KEY_FORWARD

? 57450 (0xe06a)

Key name KEY_BACK

? 57451 (0xe06b)

Key name KEY_COMPUTER

? 57452 (0xe06c)

Key name KEY_MAIL

? 57453 (0xe06d)

Key name KEY_MEDIA

? 57455 (0xe06f)

Key name KEY_MACRO

? 57456 (0xe070)

Key name KEY_DOCUMENTS

? 57457 (0xe071)

Key name KEY_BATTERY

? 57458 (0xe072)

Key name KEY_BLUETOOTH

? 57459 (0xe073)

Key name KEY_WLAN

? 57460 (0xe074)

Key name KEY_UWB

? 57461 (0xe075)

Key name KEY_HELP

? 57462 (0xe076)

Key name KEY_KPLEFTPAREN

? 57463 (0xe077)

Key name KEY_F18

? 57464 (0xe078)

Key name KEY_COPY

? 57465 (0xe079)

Key name KEY_F22

? 57467 (0xe07b)

Key name KEY_KPRIGHTPAREN

? 57469 (0xe07d)

Key name KEY_EJECTCLOSECD

VIRKEYCODE-ATSET1(7)