



Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'virkeycode-linux.7'

\$ man virkeycode-linux.7

VIRKEYCODE-LINUX(7) Virtualization Support VIRKEYCODE-LINUX(7)

NAME

virkeycode-linux - Key code values for linux

DESCRIPTION

List of linux key code values, with corresponding linux key code names

? 0 (0x0)

Key name KEY_RESERVED

? 1 (0x1)

Key name KEY_ESC

? 2 (0x2)

Key name KEY_1

? 3 (0x3)

Key name KEY_2

? 4 (0x4)

Key name KEY_3

? 5 (0x5)

Key name KEY_4

? 6 (0x6)

Key name KEY_5

? 7 (0x7)

Key name KEY_6

? 8 (0x8)

Key name KEY_7

? 9 (0x9)

Key name KEY_8

? 10 (0xa)

Key name KEY_9

? 11 (0xb)

Key name KEY_0

? 12 (0xc)

Key name KEY_MINUS

? 13 (0xd)

Key name KEY_EQUAL

? 14 (0xe)

Key name KEY_BACKSPACE

? 15 (0xf)

Key name KEY_TAB

? 16 (0x10)

Key name KEY_Q

? 17 (0x11)

Key name KEY_W

? 18 (0x12)

Key name KEY_E

? 19 (0x13)

Key name KEY_R

? 20 (0x14)

Key name KEY_T

? 21 (0x15)

Key name KEY_Y

? 22 (0x16)

Key name KEY_U

? 23 (0x17)

Key name KEY_I

? 24 (0x18)

Key name KEY_O

? 25 (0x19)

Key name KEY_P

? 26 (0x1a)

Key name KEY_LEFTBRACE

? 27 (0x1b)

Key name KEY_RIGHTBRACE

? 28 (0x1c)

Key name KEY_ENTER

? 29 (0x1d)

Key name KEY_LEFTCTRL

? 30 (0x1e)

Key name KEY_A

? 31 (0x1f)

Key name KEY_S

? 32 (0x20)

Key name KEY_D

? 33 (0x21)

Key name KEY_F

? 34 (0x22)

Key name KEY_G

? 35 (0x23)

Key name KEY_H

? 36 (0x24)

Key name KEY_J

? 37 (0x25)

Key name KEY_K

? 38 (0x26)

Key name KEY_L

? 39 (0x27)

Key name KEY_SEMICOLON

? 40 (0x28)

Key name KEY_APOSTROPHE

? 41 (0x29)

Key name KEY_GRAVE

? 42 (0x2a)

Key name KEY_LEFTSHIFT

? 43 (0x2b)

Key name KEY_BACKSLASH

? 44 (0x2c)

Key name KEY_Z

? 45 (0x2d)

Key name KEY_X

? 46 (0x2e)

Key name KEY_C

? 47 (0x2f)

Key name KEY_V

? 48 (0x30)

Key name KEY_B

? 49 (0x31)

Key name KEY_N

? 50 (0x32)

Key name KEY_M

? 51 (0x33)

Key name KEY_COMMA

? 52 (0x34)

Key name KEY_DOT

? 53 (0x35)

Key name KEY_SLASH

? 54 (0x36)

Key name KEY_RIGHTSHIFT

? 55 (0x37)

Key name KEY_KPASTERISK

? 56 (0x38)

Key name KEY_LEFTALT

? 57 (0x39)

Key name KEY_SPACE

? 58 (0x3a)

Key name KEY_CAPSLOCK

? 59 (0x3b)

Key name KEY_F1

? 60 (0x3c)

Key name KEY_F2

? 61 (0x3d)

Key name KEY_F3

? 62 (0x3e)

Key name KEY_F4

? 63 (0x3f)

Key name KEY_F5

? 64 (0x40)

Key name KEY_F6

? 65 (0x41)

Key name KEY_F7

? 66 (0x42)

Key name KEY_F8

? 67 (0x43)

Key name KEY_F9

? 68 (0x44)

Key name KEY_F10

? 69 (0x45)

Key name KEY_NUMLOCK

? 70 (0x46)

Key name KEY_SCROLLLOCK

? 71 (0x47)

Key name KEY_KP7

? 72 (0x48)

Key name KEY_KP8

? 73 (0x49)

Key name KEY_KP9

? 74 (0x4a)

Key name KEY_KPMINUS

? 75 (0x4b)

Key name KEY_KP4

? 76 (0x4c)

Key name KEY_KP5

? 77 (0x4d)

Key name KEY_KP6

? 78 (0x4e)

Key name KEY_KPPLUS

? 79 (0x4f)

Key name KEY_KP1

? 80 (0x50)

Key name KEY_KP2

? 81 (0x51)

Key name KEY_KP3

? 82 (0x52)

Key name KEY_KP0

? 83 (0x53)

Key name KEY_KPDOT

? 84 (0x54)

Key name unnamed

? 85 (0x55)

Key name KEY_ZENKAKUHANKAKU

? 86 (0x56)

Key name KEY_102ND

? 87 (0x57)

Key name KEY_F11

? 88 (0x58)

Key name KEY_F12

? 89 (0x59)

Key name KEY_RO

? 90 (0x5a)

Key name KEY_KATAKANA

? 91 (0x5b)

Key name KEY_HIRAGANA

? 92 (0x5c)

Key name KEY_HENKAN

? 93 (0x5d)

Key name KEY_KATAKANAHIRAGANA

? 94 (0x5e)

Key name KEY_MUHENKAN

? 95 (0x5f)

Key name KEY_KPJPCOMMA

? 96 (0x60)

Key name KEY_KPENTER

? 97 (0x61)

Key name KEY_RIGHTCTRL

? 98 (0x62)

Key name KEY_KPSLASH

? 99 (0x63)

Key name KEY_SYSRQ

? 100 (0x64)

Key name KEY_RIGHTALT

? 101 (0x65)

Key name KEY_LINEFEED

? 102 (0x66)

Key name KEY_HOME

? 103 (0x67)

Key name KEY_UP

? 104 (0x68)

Key name KEY_PAGEUP

? 105 (0x69)

Key name KEY_LEFT

? 106 (0x6a)

Key name KEY_RIGHT

? 107 (0x6b)

Key name KEY_END

? 108 (0x6c)

Key name KEY_DOWN

? 109 (0x6d)

Key name KEY_PAGEDOWN

? 110 (0x6e)

Key name KEY_INSERT

? 111 (0x6f)

Key name KEY_DELETE

? 112 (0x70)

Key name KEY_MACRO

? 113 (0x71)

Key name KEY_MUTE

? 114 (0x72)

Key name KEY_VOLUMEDOWN

? 115 (0x73)

Key name KEY_VOLUMEUP

? 116 (0x74)

Key name KEY_POWER

? 117 (0x75)

Key name KEY_KPEQUAL

? 118 (0x76)

Key name KEY_KPPLUSMINUS

? 119 (0x77)

Key name KEY_PAUSE

? 120 (0x78)

Key name KEY_SCALE

? 121 (0x79)

Key name KEY_KPCOMMA

? 122 (0x7a)

Key name KEY_HANGEUL

? 123 (0x7b)

Key name KEY_HANJA

? 124 (0x7c)

Key name KEY_YEN

? 125 (0x7d)

Key name KEY_LEFTMETA

? 126 (0x7e)

Key name KEY_RIGHTMETA

? 127 (0x7f)

Key name KEY_COMPOSE

? 128 (0x80)

Key name KEY_STOP

? 129 (0x81)

Key name KEY_AGAIN

? 130 (0x82)

Key name KEY_PROPS

? 131 (0x83)

Key name KEY_UNDO

? 132 (0x84)

Key name KEY_FRONT

? 133 (0x85)

Key name KEY_COPY

? 134 (0x86)

Key name KEY_OPEN

? 135 (0x87)

Key name KEY_PASTE

? 136 (0x88)

Key name KEY_FIND

? 137 (0x89)

Key name KEY_CUT

? 138 (0x8a)

Key name KEY_HELP

? 139 (0x8b)

Key name KEY_MENU

? 140 (0x8c)

Key name KEY_CALC

? 141 (0x8d)

Key name KEY_SETUP

? 142 (0x8e)

Key name KEY_SLEEP

? 143 (0x8f)

Key name KEY_WAKEUP

? 144 (0x90)

Key name KEY_FILE

? 145 (0x91)

Key name KEY_SENDFILE

? 146 (0x92)

Key name KEY_DELETEFILE

? 147 (0x93)

Key name KEY_XFER

? 148 (0x94)

Key name KEY_PROG1

? 149 (0x95)

Key name KEY_PROG2

? 150 (0x96)

Key name KEY_WWW

? 151 (0x97)

Key name KEY_MSDOS

? 152 (0x98)

Key name KEY_SCREENLOCK

? 153 (0x99)

Key name KEY_DIRECTION

? 154 (0x9a)

Key name KEY_CYCLEWINDOWS

? 155 (0x9b)

Key name KEY_MAIL

? 156 (0x9c)

Key name KEY_BOOKMARKS

? 157 (0x9d)

Key name KEY_COMPUTER

? 158 (0x9e)

Key name KEY_BACK

? 159 (0x9f)

Key name KEY_FORWARD

? 160 (0xa0)

Key name KEY_CLOSECD

? 161 (0xa1)

Key name KEY_EJECTCD

? 162 (0xa2)

Key name KEY_EJECTCLOSECD

? 163 (0xa3)

Key name KEY_NEXTSONG

? 164 (0xa4)

Key name KEY_PLAYPAUSE

? 165 (0xa5)

Key name KEY_PREVIOUSSONG

? 166 (0xa6)

Key name KEY_STOPCD

? 167 (0xa7)

Key name KEY_RECORD

? 168 (0xa8)

Key name KEY_REWIND

? 169 (0xa9)

Key name KEY_PHONE

? 170 (0xaa)

Key name KEY_ISO

? 171 (0xab)

Key name KEY_CONFIG

? 172 (0xac)

Key name KEY_HOMEPAGE

? 173 (0xad)

Key name KEY_REFRESH

? 174 (0xae)

Key name KEY_EXIT

? 175 (0xaf)

Key name KEY_MOVE

? 176 (0xb0)

Key name KEY_EDIT

? 177 (0xb1)

Key name KEY_SCROLLUP

? 178 (0xb2)

Key name KEY_SCROLLDOWN

? 179 (0xb3)

Key name KEY_KPLEFTPAREN

? 180 (0xb4)

Key name KEY_KPRIGHTPAREN

? 181 (0xb5)

Key name KEY_NEW

? 182 (0xb6)

Key name KEY_REDO

? 183 (0xb7)

Key name KEY_F13

? 184 (0xb8)

Key name KEY_F14

? 185 (0xb9)

Key name KEY_F15

? 186 (0xba)

Key name KEY_F16

? 187 (0xbb)

Key name KEY_F17

? 188 (0xbc)

Key name KEY_F18

? 189 (0xbd)

Key name KEY_F19

? 190 (0xbe)

Key name KEY_F20

? 191 (0xbf)

Key name KEY_F21

? 192 (0xc0)

Key name KEY_F22

? 193 (0xc1)

Key name KEY_F23

? 194 (0xc2)

Key name KEY_F24

? 195 (0xc3)

Key name unnamed

? 196 (0xc4)

Key name unnamed

? 197 (0xc5)

Key name unnamed

? 198 (0xc6)

Key name unnamed

? 199 (0xc7)

Key name unnamed

? 200 (0xc8)

Key name KEY_PLAYCD

? 201 (0xc9)

Key name KEY_PAUSECD

? 202 (0xca)

Key name KEY_PROG3

? 203 (0xcb)

Key name KEY_PROG4

? 204 (0xcc)

Key name KEY_DASHBOARD

? 205 (0xcd)

Key name KEY_SUSPEND

? 206 (0xce)

Key name KEY_CLOSE

? 207 (0xcf)

Key name KEY_PLAY

? 208 (0xd0)

Key name KEY_FASTFORWARD

? 209 (0xd1)

Key name KEY_BASSBOOST

? 210 (0xd2)

Key name KEY_PRINT

? 211 (0xd3)

Key name KEY_HP

? 212 (0xd4)

Key name KEY_CAMERA

? 213 (0xd5)

Key name KEY_SOUND

? 214 (0xd6)

Key name KEY_QUESTION

? 215 (0xd7)

Key name KEY_EMAIL

? 216 (0xd8)

Key name KEY_CHAT

? 217 (0xd9)

Key name KEY_SEARCH

? 218 (0xda)

Key name KEY_CONNECT

? 219 (0xdb)

Key name KEY_FINANCE

? 220 (0xdc)

Key name KEY_SPORT

? 221 (0xdd)

Key name KEY_SHOP

? 222 (0xde)

Key name KEY_ALTERASE

? 223 (0xdf)

Key name KEY_CANCEL

? 224 (0xe0)

Key name KEY_BRIGHTNESSDOWN

? 225 (0xe1)

Key name KEY_BRIGHTNESSUP

? 226 (0xe2)

Key name KEY_MEDIA

? 227 (0xe3)

Key name KEY_SWITCHVIDEOMODE

? 228 (0xe4)

Key name KEY_KBDILLUMTOGGLE

? 229 (0xe5)

Key name KEY_KBDILLUMDOWN

? 230 (0xe6)

Key name KEY_KBDILLUMUP

? 231 (0xe7)

Key name KEY_SEND

? 232 (0xe8)

Key name KEY_REPLY

? 233 (0xe9)

Key name KEY_FORWARDMAIL

? 234 (0xea)

Key name KEY_SAVE

? 235 (0xeb)

Key name KEY_DOCUMENTS

? 236 (0xec)

Key name KEY_BATTERY

? 237 (0xed)

Key name KEY_BLUETOOTH

? 238 (0xee)

Key name KEY_WLAN

? 239 (0xef)

Key name KEY_UWB

? 240 (0xf0)

Key name KEY_UNKNOWN

? 241 (0xf1)

Key name KEY_VIDEO_NEXT

? 242 (0xf2)

Key name KEY_VIDEO_PREV

? 243 (0xf3)

Key name KEY_BRIGHTNESS_CYCLE

? 244 (0xf4)

Key name KEY_BRIGHTNESS_ZERO

? 245 (0xf5)

Key name KEY_DISPLAY_OFF

? 246 (0xf6)

Key name KEY_WIMAX

? 247 (0xf7)

Key name unnamed

? 248 (0xf8)

Key name unnamed

? 249 (0xf9)

Key name unnamed

? 250 (0xfa)

Key name unnamed

? 251 (0xfb)

Key name unnamed

? 252 (0xfc)

Key name unnamed

? 253 (0xfd)

Key name unnamed

? 254 (0xfe)

Key name unnamed

? 255 (0xff)

Key name unnamed

? 256 (0x100)

Key name BTN_0

? 257 (0x101)

Key name BTN_1

? 258 (0x102)

Key name BTN_2

? 259 (0x103)

Key name BTN_3

? 260 (0x104)

Key name BTN_4

? 261 (0x105)

Key name BTN_5

? 262 (0x106)

Key name BTN_6

? 263 (0x107)

Key name BTN_7

? 264 (0x108)

Key name BTN_8

? 265 (0x109)

Key name BTN_9

? 272 (0x110)

Key name BTN_LEFT

? 273 (0x111)

Key name BTN_RIGHT

? 274 (0x112)

Key name BTN_MIDDLE

? 275 (0x113)

Key name BTN_SIDE

? 276 (0x114)

Key name BTN_EXTRA

? 277 (0x115)

Key name BTN_FORWARD

? 278 (0x116)

Key name BTN_BACK

? 279 (0x117)

Key name BTN_TASK

? 288 (0x120)

Key name BTN_TRIGGER

? 289 (0x121)

Key name BTN_THUMB

? 290 (0x122)

Key name BTN_THUMB2

? 291 (0x123)

Key name BTN_TOP

? 292 (0x124)

Key name BTN_TOP2

? 293 (0x125)

Key name BTN_PINKIE

? 294 (0x126)

Key name BTN_BASE

? 295 (0x127)

Key name BTN_BASE2

? 296 (0x128)

Key name BTN_BASE3

? 297 (0x129)

Key name BTN_BASE4

? 298 (0x12a)

Key name BTN_BASE5

? 299 (0x12b)

Key name BTN_BASE6

? 303 (0x12f)

Key name BTN_DEAD

? 304 (0x130)

Key name BTN_A

? 305 (0x131)

Key name BTN_B

? 306 (0x132)

Key name BTN_C

? 307 (0x133)

Key name BTN_X

? 308 (0x134)

Key name BTN_Y

? 309 (0x135)

Key name BTN_Z

? 310 (0x136)

Key name BTN_TL

? 311 (0x137)

Key name BTN_TR

? 312 (0x138)

Key name BTN_TL2

? 313 (0x139)

Key name BTN_TR2

? 314 (0x13a)

Key name BTN_SELECT

? 315 (0x13b)

Key name BTN_START

? 316 (0x13c)

Key name BTN_MODE

? 317 (0x13d)

Key name BTN_THUMBL

? 318 (0x13e)

Key name BTN_THUMBR

? 320 (0x140)

Key name BTN_TOOL_PEN

? 321 (0x141)

Key name BTN_TOOL_RUBBER

? 322 (0x142)

Key name BTN_TOOL_BRUSH

? 323 (0x143)

Key name BTN_TOOL_PENCIL

? 324 (0x144)

Key name BTN_TOOL_AIRBRUSH

? 325 (0x145)

Key name BTN_TOOL_FINGER

? 326 (0x146)

Key name BTN_TOOL_MOUSE

? 327 (0x147)

Key name BTN_TOOL_LENS

? 330 (0x14a)

Key name BTN_TOUCH

? 331 (0x14b)

Key name BTN_STYLUS

? 332 (0x14c)

Key name BTN_STYLUS2

? 333 (0x14d)

Key name BTN_TOOL_DOUBLETAP

? 334 (0x14e)

Key name BTN_TOOL_TRIPLETAP

? 335 (0x14f)

Key name BTN_TOOL_QUADTAP

? 336 (0x150)

Key name BTN_GEAR_DOWN

? 337 (0x151)

Key name BTN_GEAR_UP

? 352 (0x160)

Key name KEY_OK

? 353 (0x161)

Key name KEY_SELECT

? 354 (0x162)

Key name KEY_GOTO

? 355 (0x163)

Key name KEY_CLEAR

? 356 (0x164)

Key name KEY_POWER2

? 357 (0x165)

Key name KEY_OPTION

? 358 (0x166)

Key name KEY_INFO

? 359 (0x167)

Key name KEY_TIME

? 360 (0x168)

Key name KEY_VENDOR

? 361 (0x169)

Key name KEY_ARCHIVE

? 362 (0x16a)

Key name KEY_PROGRAM

? 363 (0x16b)

Key name KEY_CHANNEL

? 364 (0x16c)

Key name KEY_FAVORITES

? 365 (0x16d)

Key name KEY_EPG

? 366 (0x16e)

Key name KEY_PVR

? 367 (0x16f)

Key name KEY_MHP

? 368 (0x170)

Key name KEY_LANGUAGE

? 369 (0x171)

Key name KEY_TITLE

? 370 (0x172)

Key name KEY_SUBTITLE

? 371 (0x173)

Key name KEY_ANGLE

? 372 (0x174)

Key name KEY_ZOOM

? 373 (0x175)

Key name KEY_MODE

? 374 (0x176)

Key name KEY_KEYBOARD

? 375 (0x177)

Key name KEY_SCREEN

? 376 (0x178)

Key name KEY_PC

? 377 (0x179)

Key name KEY_TV

? 378 (0x17a)

Key name KEY_TV2

? 379 (0x17b)

Key name KEY_VCR

? 380 (0x17c)

Key name KEY_VCR2

? 381 (0x17d)

Key name KEY_SAT

? 382 (0x17e)

Key name KEY_SAT2

? 383 (0x17f)

Key name KEY_CD

? 384 (0x180)

Key name KEY_TAPE

? 385 (0x181)

Key name KEY_RADIO

? 386 (0x182)

Key name KEY_TUNER

? 387 (0x183)

Key name KEY_PLAYER

? 388 (0x184)

Key name KEY_TEXT

? 389 (0x185)

Key name KEY_DVD

? 390 (0x186)

Key name KEY_AUX

? 391 (0x187)

Key name KEY_MP3

? 392 (0x188)

Key name KEY_AUDIO

? 393 (0x189)

Key name KEY_VIDEO

? 394 (0x18a)

Key name KEY_DIRECTORY

? 395 (0x18b)

Key name KEY_LIST

? 396 (0x18c)

Key name KEY_MEMO

? 397 (0x18d)

Key name KEY_CALENDAR

? 398 (0x18e)

Key name KEY_RED

? 399 (0x18f)

Key name KEY_GREEN

? 400 (0x190)

Key name KEY_YELLOW

? 401 (0x191)

Key name KEY_BLUE

? 402 (0x192)

Key name KEY_CHANNELUP

? 403 (0x193)

Key name KEY_CHANNELDOWN

? 404 (0x194)

Key name KEY_FIRST

? 405 (0x195)

Key name KEY_LAST

? 406 (0x196)

Key name KEY_AB

? 407 (0x197)

Key name KEY_NEXT

? 408 (0x198)

Key name KEY_RESTART

? 409 (0x199)

Key name KEY_SLOW

? 410 (0x19a)

Key name KEY_SHUFFLE

? 411 (0x19b)

Key name KEY_BREAK

? 412 (0x19c)

Key name KEY_PREVIOUS

? 413 (0x19d)

Key name KEY_DIGITS

? 414 (0x19e)

Key name KEY_TEEN

? 415 (0x19f)

Key name KEY_TWEN

? 416 (0x1a0)

Key name KEY_VIDEOPHONE

? 417 (0x1a1)

Key name KEY_GAMES

? 418 (0x1a2)

Key name KEY_ZOOMIN

? 419 (0x1a3)

Key name KEY_ZOOMOUT

? 420 (0x1a4)

Key name KEY_ZOOMRESET

? 421 (0x1a5)

Key name KEY_WORDPROCESSOR

? 422 (0x1a6)

Key name KEY_EDITOR

? 423 (0x1a7)

Key name KEY_SPREADSHEET

? 424 (0x1a8)

Key name KEY_GRAPHICSEEDITOR

? 425 (0x1a9)

Key name KEY_PRESENTATION

? 426 (0x1aa)

Key name KEY_DATABASE

? 427 (0x1ab)

Key name KEY_NEWS

? 428 (0x1ac)

Key name KEY_VOICEMAIL

? 429 (0x1ad)

Key name KEY_ADDRESSBOOK

? 430 (0x1ae)

Key name KEY_MESSENGER

? 431 (0x1af)

Key name KEY_DISPLAYTOGGLE

? 432 (0x1b0)

Key name KEY_SPELLCHECK

? 433 (0x1b1)

Key name KEY_LOGOFF

? 434 (0x1b2)

Key name KEY_DOLLAR

? 435 (0x1b3)

Key name KEY_EURO

? 436 (0x1b4)

Key name KEY_FRAMEBACK

? 437 (0x1b5)

Key name KEY_FRAMEFORWARD

? 438 (0x1b6)

Key name KEY_CONTEXT_MENU

? 439 (0x1b7)

Key name KEY_MEDIA_REPEAT

? 448 (0x1c0)

Key name KEY_DEL_EOL

? 449 (0x1c1)

Key name KEY_DEL_EOS

? 450 (0x1c2)

Key name KEY_INS_LINE

? 451 (0x1c3)

Key name KEY_DEL_LINE

? 464 (0x1d0)

Key name KEY_FN

? 465 (0x1d1)

Key name KEY_FN_ESC

? 466 (0x1d2)

Key name KEY_FN_F1

? 467 (0x1d3)

Key name KEY_FN_F2

? 468 (0x1d4)

Key name KEY_FN_F3

? 469 (0x1d5)

Key name KEY_FN_F4

? 470 (0x1d6)

Key name KEY_FN_F5

? 471 (0x1d7)

Key name KEY_FN_F6

? 472 (0x1d8)

Key name KEY_FN_F7

? 473 (0x1d9)

Key name KEY_FN_F8

? 474 (0x1da)

Key name KEY_FN_F9

? 475 (0x1db)

Key name KEY_FN_F10

? 476 (0x1dc)

Key name KEY_FN_F11

? 477 (0x1dd)

Key name KEY_FN_F12

? 478 (0x1de)

Key name KEY_FN_1

? 479 (0x1df)

Key name KEY_FN_2

? 480 (0x1e0)

Key name KEY_FN_D

? 481 (0x1e1)

Key name KEY_FN_E

? 482 (0x1e2)

Key name KEY_FN_F

? 483 (0x1e3)

Key name KEY_FN_S

? 484 (0x1e4)

Key name KEY_FN_B

? 497 (0x1f1)

Key name KEY_BRL_DOT1

? 498 (0x1f2)

Key name KEY_BRL_DOT2

? 499 (0x1f3)

Key name KEY_BRL_DOT3

? 500 (0x1f4)

Key name KEY_BRL_DOT4

? 501 (0x1f5)

Key name KEY_BRL_DOT5

? 502 (0x1f6)

Key name KEY_BRL_DOT6

? 503 (0x1f7)

Key name KEY_BRL_DOT7

? 504 (0x1f8)

Key name KEY_BRL_DOT8

? 505 (0x1f9)

Key name KEY_BRL_DOT9

? 506 (0x1fa)

Key name KEY_BRL_DOT10

? 512 (0x200)

Key name KEY_NUMERIC_0

? 513 (0x201)

Key name KEY_NUMERIC_1

? 514 (0x202)

Key name KEY_NUMERIC_2

? 515 (0x203)

Key name KEY_NUMERIC_3

? 516 (0x204)

Key name KEY_NUMERIC_4

? 517 (0x205)

Key name KEY_NUMERIC_5

? 518 (0x206)

Key name KEY_NUMERIC_6

? 519 (0x207)

Key name KEY_NUMERIC_7

? 520 (0x208)

Key name KEY_NUMERIC_8

? 521 (0x209)

Key name KEY_NUMERIC_9

? 522 (0x20a)

Key name KEY_NUMERIC_STAR

? 523 (0x20b)

Key name KEY_NUMERIC_POUND

? 524 (0x20c)

Key name KEY_RFKILL

VIRKEYCODE-LINUX(7)