



Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'virkeycode-usb.7'

\$ man virkeycode-usb.7

VIRKEYCODE-USB(7) Virtualization Support VIRKEYCODE-USB(7)

NAME

virkeycode-usb - Key code values for usb

DESCRIPTION

List of usb key code values, with corresponding linux key code names

? 4 (0x4)

Key name KEY_A

? 5 (0x5)

Key name KEY_B

? 6 (0x6)

Key name KEY_C

? 7 (0x7)

Key name KEY_D

? 8 (0x8)

Key name KEY_E

? 9 (0x9)

Key name KEY_F

? 10 (0xa)

Key name KEY_G

? 11 (0xb)

Key name KEY_H

? 12 (0xc)

Key name KEY_I

? 13 (0xd)

Key name KEY_J

? 14 (0xe)

Key name KEY_K

? 15 (0xf)

Key name KEY_L

? 16 (0x10)

Key name KEY_M

? 17 (0x11)

Key name KEY_N

? 18 (0x12)

Key name KEY_O

? 19 (0x13)

Key name KEY_P

? 20 (0x14)

Key name KEY_Q

? 21 (0x15)

Key name KEY_R

? 22 (0x16)

Key name KEY_S

? 23 (0x17)

Key name KEY_T

? 24 (0x18)

Key name KEY_U

? 25 (0x19)

Key name KEY_V

? 26 (0x1a)

Key name KEY_W

? 27 (0x1b)

Key name KEY_X

? 28 (0x1c)

Key name KEY_Y

? 29 (0x1d)

Key name KEY_Z

? 30 (0x1e)

Key name KEY_1

? 31 (0x1f)

Key name KEY_2

? 32 (0x20)

Key name KEY_3

? 33 (0x21)

Key name KEY_4

? 34 (0x22)

Key name KEY_5

? 35 (0x23)

Key name KEY_6

? 36 (0x24)

Key name KEY_7

? 37 (0x25)

Key name KEY_8

? 38 (0x26)

Key name KEY_9

? 39 (0x27)

Key name KEY_0

? 40 (0x28)

Key name KEY_ENTER

? 41 (0x29)

Key name KEY_ESC

? 42 (0x2a)

Key name KEY_BACKSPACE

? 43 (0x2b)

Key name KEY_TAB

? 44 (0x2c)

Key name KEY_SPACE

? 45 (0x2d)

Key name KEY_MINUS

? 46 (0x2e)

Key name KEY_EQUAL

? 47 (0x2f)

Key name KEY_LEFTBRACE

? 48 (0x30)

Key name KEY_RIGHTBRACE

? 49 (0x31)

Key name KEY_BACKSLASH

? 50 (0x32)

Key name KEY_BACKSLASH

? 51 (0x33)

Key name KEY_SEMICOLON

? 52 (0x34)

Key name KEY_APOSTROPHE

? 53 (0x35)

Key name KEY_GRAVE

? 54 (0x36)

Key name KEY_COMMA

? 55 (0x37)

Key name KEY_DOT

? 56 (0x38)

Key name KEY_SLASH

? 57 (0x39)

Key name KEY_CAPSLOCK

? 58 (0x3a)

Key name KEY_F1

? 59 (0x3b)

Key name KEY_F2

? 60 (0x3c)

Key name KEY_F3

? 61 (0x3d)

Key name KEY_F4

? 62 (0x3e)

Key name KEY_F5

? 63 (0x3f)

Key name KEY_F6

? 64 (0x40)

Key name KEY_F7

? 65 (0x41)

Key name KEY_F8

? 66 (0x42)

Key name KEY_F9

? 67 (0x43)

Key name KEY_F10

? 68 (0x44)

Key name KEY_F11

? 69 (0x45)

Key name KEY_F12

? 70 (0x46)

Key name KEY_SYSRQ

? 71 (0x47)

Key name KEY_SCROLLLOCK

? 72 (0x48)

Key name KEY_PAUSE

? 73 (0x49)

Key name KEY_INSERT

? 74 (0x4a)

Key name KEY_HOME

? 75 (0x4b)

Key name KEY_PAGEUP

? 76 (0x4c)

Key name KEY_DELETE

? 77 (0x4d)

Key name KEY_END

? 78 (0x4e)

Key name KEY_PAGEDOWN

? 79 (0x4f)

Key name KEY_RIGHT

? 80 (0x50)

Key name KEY_LEFT

? 81 (0x51)

Key name KEY_DOWN

? 82 (0x52)

Key name KEY_UP

? 83 (0x53)

Key name KEY_NUMLOCK

? 84 (0x54)

Key name KEY_KPSLASH

? 85 (0x55)

Key name KEY_KPASTERISK

? 86 (0x56)

Key name KEY_KPMINUS

? 87 (0x57)

Key name KEY_KPPLUS

? 88 (0x58)

Key name KEY_KPENTER

? 89 (0x59)

Key name KEY_KP1

? 90 (0x5a)

Key name KEY_KP2

? 91 (0x5b)

Key name KEY_KP3

? 92 (0x5c)

Key name KEY_KP4

? 93 (0x5d)

Key name KEY_KP5

? 94 (0x5e)

Key name KEY_KP6

? 95 (0x5f)

Key name KEY_KP7

? 96 (0x60)

Key name KEY_KP8

? 97 (0x61)

Key name KEY_KP9

? 98 (0x62)

Key name KEY_KP0

? 99 (0x63)

Key name KEY_KPDOT

? 100 (0x64)

Key name KEY_102ND

? 101 (0x65)

Key name KEY_COMPOSE

? 102 (0x66)

Key name KEY_POWER

? 103 (0x67)

Key name KEY_KPEQUAL

? 104 (0x68)

Key name KEY_F13

? 105 (0x69)

Key name KEY_F14

? 106 (0x6a)

Key name KEY_F15

? 107 (0x6b)

Key name KEY_F16

? 108 (0x6c)

Key name KEY_F17

? 109 (0x6d)

Key name KEY_F18

? 110 (0x6e)

Key name KEY_F19

? 111 (0x6f)

Key name KEY_F20

? 112 (0x70)

Key name KEY_F21

? 113 (0x71)

Key name KEY_F22

? 114 (0x72)

Key name KEY_F23

? 115 (0x73)

Key name KEY_F24

? 116 (0x74)

Key name KEY_OPEN

? 117 (0x75)

Key name KEY_HELP

? 118 (0x76)

Key name KEY_MENU

? 119 (0x77)

Key name KEY_FRONT

? 120 (0x78)

Key name KEY_STOP

? 121 (0x79)

Key name KEY_AGAIN

? 122 (0x7a)

Key name KEY_UNDO

? 123 (0x7b)

Key name KEY_CUT

? 124 (0x7c)

Key name KEY_COPY

? 125 (0x7d)

Key name KEY_PASTE

? 126 (0x7e)

Key name KEY_FIND

? 127 (0x7f)

Key name KEY_MUTE

? 128 (0x80)

Key name KEY_VOLUMEUP

? 129 (0x81)

Key name KEY_VOLUMEDOWN

? 133 (0x85)

Key name KEY_KPCOMMA

? 135 (0x87)

Key name KEY_RO

? 136 (0x88)

Key name KEY_KATAKANAHIRAGANA

? 137 (0x89)

Key name KEY_YEN

? 138 (0x8a)

Key name KEY_HENKAN

? 139 (0x8b)

Key name KEY_MUHENKAN

? 140 (0x8c)

Key name KEY_KPJPCOMMA

? 144 (0x90)

Key name KEY_HANGEUL

? 145 (0x91)

Key name KEY_HANJA

? 146 (0x92)

Key name KEY_KATAKANA

? 147 (0x93)

Key name KEY_HIRAGANA

? 148 (0x94)

Key name KEY_ZENKAKUHANKAKU

? 182 (0xb6)

Key name KEY_KPLEFTPAREN

? 183 (0xb7)

Key name KEY_KPRIGHTPAREN

? 224 (0xe0)

Key name KEY_LEFTCTRL

? 225 (0xe1)

Key name KEY_LEFTSHIFT

? 226 (0xe2)

Key name KEY_LEFTALT

? 227 (0xe3)

Key name KEY_LEFTMETA

? 228 (0xe4)

Key name KEY_RIGHTCTRL

? 229 (0xe5)

Key name KEY_RIGHTSHIFT

? 230 (0xe6)

Key name KEY_RIGHTALT

? 231 (0xe7)

Key name KEY_RIGHTMETA

? 232 (0xe8)

Key name KEY_PLAYPAUSE

? 233 (0xe9)

Key name KEY_STOPCD

? 234 (0xea)

Key name KEY_PREVIOUSSONG

? 235 (0xeb)

Key name KEY_NEXTSONG

? 236 (0xec)

Key name KEY_EJECTCD

? 237 (0xed)

Key name KEY_VOLUMEUP

? 238 (0xee)

Key name KEY_VOLUMEDOWN

? 239 (0xef)

Key name KEY_MUTE

? 240 (0xf0)

Key name KEY_WWW

? 241 (0xf1)

Key name KEY_BACK

? 242 (0xf2)

Key name KEY_FORWARD

? 243 (0xf3)

Key name KEY_STOP

? 244 (0xf4)

Key name KEY_FIND

? 245 (0xf5)

Key name KEY_SCROLLUP

? 246 (0xf6)

Key name KEY_SCROLLDOWN

? 247 (0xf7)

Key name KEY_EDIT

? 248 (0xf8)

Key name KEY_SLEEP

? 249 (0xf9)

Key name KEY_SCREENLOCK

? 250 (0xfa)

Key name KEY_REFRESH

? 251 (0xfb)

Key name KEY_CALC

VIRKEYCODE-USB(7)