NAME

      rdma − RDMA tool

SYNOPSIS

      rdma [*OPTIONS*] *OBJECT* { *COMMAND* | **help** }

      rdma [**-force**] **-batch** *filename*

      OBJECT := { **dev** | **link** | **system** | **statistic** }

      OPTIONS := { −**V**[*ersion*] | −**d**[*etails*] } −**j**[*son*] } −**p**[*retty*] }

OPTIONS

      −**V**, **-Version**

            Print the version of the **rdma** tool and exit.

      −**b**, −**batch** <FILENAME>

            Read commands from provided file or standard input and invoke them. First failure will cause ter-
            mination of rdma.

      −**force** Don't terminate rdma on errors in batch mode. If there were any errors during execution of the
            commands, the application return code will be non zero.

      −**d**, **--details**

            Output detailed information. Adding a second −d includes driver-specific details.

      −**p**, **--pretty**

            When combined with -j generate a pretty JSON output.

      −**j**, **--json**

            Generate JSON output.

    OBJECT

      dev   - RDMA device.

      link   - RDMA port related.

      sys   - RDMA subsystem related.

      statistic

            - RDMA counter statistic related.

      The names of all objects may be written in full or abbreviated form, for example **stats** can be abbreviated as
      stat or just **s.**

COMMAND
> Specifies the action to perform on the object. The set of possible actions depends on the object type. As a rule, it is possible to **show** (or **list**) objects, but some objects do not allow all of these operations or have some additional commands. The **help** command is available for all objects. It prints out a list of available commands and argument syntax conventions.
>
> If no command is given, some default command is assumed. Usually it is **list** or, if the objects of this class cannot be listed, **help**.

EXIT STATUS
> Exit status is 0 if command was successful or a positive integer upon failure.

SEE ALSO
> **rdma-dev**(8), **rdma-link**(8), **rdma-resource**(8), **rdma-system**(8), **rdma-statistic**(8),

REPORTING BUGS
> Report any bugs to the Linux RDMA mailing list **<linux-rdma@vger.kernel.org>** where the development and maintenance is primarily done. You do not have to be subscribed to the list to send a message there.

AUTHOR
> Leon Romanovsky <leonro@mellanox.com>