

NAME

virkeycode-atset1 – Key code values for atset1

DESCRIPTION

List of atset1 key code values, with corresponding linux key code names

- 1 (0x1)

Key name KEY_ESC

- 2 (0x2)

Key name KEY_1

- 3 (0x3)

Key name KEY_2

- 4 (0x4)

Key name KEY_3

- 5 (0x5)

Key name KEY_4

- 6 (0x6)

Key name KEY_5

- 7 (0x7)

Key name KEY_6

- 8 (0x8)

Key name KEY_7

- 9 (0x9)

Key name KEY_8

- 10 (0xa)

Key name KEY_9

- 11 (0xb)

Key name KEY_0

- 12 (0xc)

Key name KEY_MINUS

- 13 (0xd)

Key name KEY_EQUAL

- 14 (0xe)

Key name KEY_BACKSPACE

- 15 (0xf)

Key name KEY_TAB

- 16 (0x10)

Key name KEY_Q

- 17 (0x11)

Key name KEY_W

- 18 (0x12)

Key name KEY_E

- 19 (0x13)

Key name KEY_R

- 20 (0x14)

Key name KEY_T

- 21 (0x15)

Key name KEY_Y

- 22 (0x16)

Key name KEY_U

- 23 (0x17)

Key name KEY_I

- 24 (0x18)

Key name KEY_O

- 25 (0x19)

Key name KEY_P

- 26 (0x1a)

Key name KEY_LEFTBRACE

- 27 (0x1b)

Key name KEY_RIGHTBRACE

- 28 (0x1c)

Key name KEY_ENTER

- 29 (0x1d)

Key name KEY_LEFTCTRL

- 30 (0x1e)

Key name KEY_A

- 31 (0x1f)

Key name KEY_S

- 32 (0x20)

Key name KEY_D

- 33 (0x21)

Key name KEY_F

- 34 (0x22)

Key name KEY_G

- 35 (0x23)

Key name KEY_H

- 36 (0x24)

Key name KEY_J

- 37 (0x25)

Key name KEY_K

- 38 (0x26)

Key name KEY_L

- 39 (0x27)

Key name KEY_SEMICOLON

- 40 (0x28)

Key name KEY_APOSTROPHE

- 41 (0x29)

Key name KEY_GRAVE

- 42 (0x2a)

Key name KEY_LEFTSHIFT

- 43 (0x2b)

Key name KEY_BACKSLASH

- 44 (0x2c)

Key name KEY_Z

- 45 (0x2d)

Key name KEY_X

- 46 (0x2e)

Key name KEY_C

- 47 (0x2f)

Key name KEY_V

- 48 (0x30)

Key name KEY_B

- 49 (0x31)

Key name KEY_N

- 50 (0x32)

Key name KEY_M

- 51 (0x33)

Key name KEY_COMMA

- 52 (0x34)

Key name KEY_DOT

- 53 (0x35)

Key name KEY_SLASH

- 54 (0x36)

Key name KEY_RIGHTSHIFT

- 55 (0x37)

Key name KEY_KPASTERISK

- 56 (0x38)

Key name KEY_LEFTALT

- 57 (0x39)

Key name KEY_SPACE

- 58 (0x3a)

Key name KEY_CAPSLOCK

- 59 (0x3b)

Key name KEY_F1

- 60 (0x3c)

Key name KEY_F2

- 61 (0x3d)

Key name KEY_F3

- 62 (0x3e)

Key name KEY_F4

- 63 (0x3f)

Key name KEY_F5

- 64 (0x40)

Key name KEY_F6

- 65 (0x41)

Key name KEY_F7

- 66 (0x42)

Key name KEY_F8

- 67 (0x43)

Key name KEY_F9

- 68 (0x44)

Key name KEY_F10

- 69 (0x45)

Key name KEY_NUMLOCK

- 70 (0x46)

Key name KEY_SCROLLLOCK

- 71 (0x47)

Key name KEY_KP7

- 72 (0x48)

Key name KEY_KP8

- 73 (0x49)

Key name KEY_KP9

- 74 (0x4a)

Key name KEY_KPMINUS

- 75 (0x4b)

Key name KEY_KP4

- 76 (0x4c)

Key name KEY_KP5

- 77 (0x4d)

Key name KEY_KP6

- 78 (0x4e)

Key name KEY_KPPLUS

- 79 (0x4f)

Key name KEY_KP1

- 80 (0x50)

Key name KEY_KP2

- 81 (0x51)

Key name KEY_KP3

- 82 (0x52)

Key name KEY_KP0

- 83 (0x53)

Key name KEY_KPDOT

- 84 (0x54)

Key name KEY_SYSRQ

- 85 (0x55)

Key name KEY_F16

- 86 (0x56)

Key name KEY_102ND

- 87 (0x57)

Key name KEY_F11

- 88 (0x58)

Key name KEY_F12

- 89 (0x59)

Key name KEY_KPEQUAL

- 90 (0x5a)

Key name KEY_F20

- 91 (0x5b)

Key name KEY_LINEFEED

- 92 (0x5c)

Key name KEY_KPJPCOMMA

- 93 (0x5d)

Key name KEY_F13

- 94 (0x5e)

Key name KEY_F14

- 95 (0x5f)

Key name KEY_F15

- 99 (0x63)

Key name KEY_PHONE

- 100 (0x64)

Key name KEY_OPEN

- 101 (0x65)

Key name KEY_PASTE

- 102 (0x66)

Key name KEY_SETUP

- 103 (0x67)

Key name KEY_FILE

- 104 (0x68)

Key name KEY_SENDFILE

- 105 (0x69)

Key name KEY_DELETEFILE

- 106 (0x6a)

Key name KEY_MSDOS

- 107 (0x6b)

Key name KEY_DIRECTION

- 108 (0x6c)

Key name KEY_EJECTCD

- 109 (0x6d)

Key name KEY_F23

- 111 (0x6f)

Key name KEY_F24

- 112 (0x70)

Key name KEY_KATAKANAHIRAGANA

- 113 (0x71)

Key name KEY_EXIT

- 114 (0x72)

Key name KEY_MOVE

- 115 (0x73)

Key name KEY_RO

- 116 (0x74)

Key name KEY_F21

- 117 (0x75)

Key name KEY_SCROLLUP

- 118 (0x76)

Key name KEY_ZENKAKUHANKAKU

- 119 (0x77)

Key name KEY_HIRAGANA

- 120 (0x78)

Key name KEY_KATAKANA

- 121 (0x79)

Key name KEY_HENKAN

- 123 (0x7b)

Key name KEY_MUHENKAN

- 125 (0x7d)

Key name KEY_YEN

- 126 (0x7e)

Key name KEY_KPCOMMA

- 57345 (0xe001)

Key name KEY_CONFIG

- 57346 (0xe002)

Key name KEY_WWW

- 57347 (0xe003)

Key name KEY_F17

- 57348 (0xe004)

Key name KEY_F19

- 57349 (0xe005)

Key name KEY_AGAIN

- 57350 (0xe006)

Key name KEY_PROPS

- 57351 (0xe007)

Key name KEY_UNDO

- 57352 (0xe008)

Key name KEY_EDIT

- 57353 (0xe009)

Key name KEY_NEW

- 57354 (0xe00a)

Key name KEY_REDO

- 57355 (0xe00b)

Key name KEY_SCALE

- 57356 (0xe00c)

Key name KEY_FRONT

- 57357 (0xe00d)

Key name KEY_HANJA

- 57358 (0xe00e)

Key name KEY_FORWARDMAIL

- 57359 (0xe00f)

Key name KEY_SCROLLDOWN

- 57360 (0xe010)

Key name KEY_PREVIOUSSONG

- 57362 (0xe012)

Key name KEY_SCREENLOCK

- 57363 (0xe013)

Key name KEY_XFER

- 57364 (0xe014)

Key name KEY_ALTERASE

- 57365 (0xe015)

Key name unnamed

- 57366 (0xe016)

Key name unnamed

- 57367 (0xe017)

Key name KEY_PROG2

- 57368 (0xe018)

Key name KEY_REWIND

- 57369 (0xe019)

Key name KEY_NEXTSONG

- 57370 (0xe01a)

Key name unnamed

- 57371 (0xe01b)

Key name unnamed

- 57372 (0xe01c)

Key name KEY_KPENTER

- 57373 (0xe01d)

Key name KEY_RIGHTCTRL

- 57374 (0xe01e)

Key name KEY_MENU

- 57375 (0xe01f)

Key name KEY_PROG1

- 57376 (0xe020)

Key name KEY_MUTE

- 57377 (0xe021)

Key name KEY_CALC

- 57378 (0xe022)

Key name KEY_PLAYPAUSE

- 57379 (0xe023)

Key name KEY_CLOSECD

- 57380 (0xe024)

Key name KEY_STOPCD

- 57381 (0xe025)

Key name KEY_SUSPEND

- 57382 (0xe026)

Key name KEY_CYCLEWINDOWS

- 57383 (0xe027)

Key name unnamed

- 57384 (0xe028)

Key name KEY_PLAYCD

- 57385 (0xe029)

Key name KEY_PAUSECD

- 57387 (0xe02b)

Key name KEY_PROG3

- 57388 (0xe02c)

Key name KEY_PROG4

- 57389 (0xe02d)

Key name KEY_DASHBOARD

- 57390 (0xe02e)

Key name KEY_VOLUMEDOWN

- 57391 (0xe02f)

Key name KEY_CLOSE

- 57392 (0xe030)

Key name KEY_VOLUMEUP

- 57393 (0xe031)

Key name KEY_RECORD

- 57394 (0xe032)

Key name KEY_HOMEPAGE

- 57395 (0xe033)

Key name KEY_PLAY

- 57396 (0xe034)

Key name KEY_FASTFORWARD

- 57397 (0xe035)

Key name KEY_KPSLASH

- 57398 (0xe036)

Key name KEY_BASSBOOST

- 57400 (0xe038)

Key name KEY_RIGHTALT

- 57401 (0xe039)

Key name KEY_PRINT

- 57402 (0xe03a)

Key name KEY_HP

- 57403 (0xe03b)

Key name KEY_CAMERA

- 57404 (0xe03c)

Key name KEY_CUT

- 57405 (0xe03d)

Key name KEY_SOUND

- 57406 (0xe03e)

Key name KEY_QUESTION

- 57407 (0xe03f)

Key name KEY_EMAIL

- 57408 (0xe040)

Key name KEY_CHAT

- 57409 (0xe041)

Key name KEY_FIND

- 57410 (0xe042)

Key name KEY_CONNECT

- 57411 (0xe043)

Key name KEY_FINANCE

- 57412 (0xe044)

Key name KEY_SPORT

- 57413 (0xe045)

Key name KEY_SHOP

- 57414 (0xe046)

Key name KEY_PAUSE

- 57415 (0xe047)

Key name KEY_HOME

- 57416 (0xe048)

Key name KEY_UP

- 57417 (0xe049)

Key name KEY_PAGEUP

- 57418 (0xe04a)

Key name KEY_CANCEL

- 57419 (0xe04b)

Key name KEY_LEFT

- 57420 (0xe04c)

Key name KEY_BRIGHTNESSDOWN

- 57421 (0xe04d)

Key name KEY_RIGHT

- 57422 (0xe04e)

Key name KEY_KPPLUSMINUS

- 57423 (0xe04f)

Key name KEY_END

- 57424 (0xe050)

Key name KEY_DOWN

- 57425 (0xe051)

Key name KEY_PAGEDOWN

- 57426 (0xe052)

Key name KEY_INSERT

- 57427 (0xe053)

Key name KEY_DELETE

- 57428 (0xe054)

Key name KEY_BRIGHTNESSUP

- 57429 (0xe055)

Key name KEY_SAVE

- 57430 (0xe056)

Key name KEY_SWITCHVIDEOMODE

- 57431 (0xe057)

Key name KEY_KBDILLUMTOGGLE

- 57432 (0xe058)

Key name KEY_KBDILLUMDOWN

- 57433 (0xe059)

Key name KEY_KBDILLUMUP

- 57434 (0xe05a)

Key name KEY_SEND

- 57435 (0xe05b)

Key name KEY_LEFTMETA

- 57436 (0xe05c)

Key name KEY_RIGHTMETA

- 57437 (0xe05d)

Key name KEY_COMPOSE

- 57438 (0xe05e)

Key name KEY_POWER

- 57439 (0xe05f)

Key name KEY_SLEEP

- 57443 (0xe063)

Key name KEY_WAKEUP

- 57444 (0xe064)

Key name KEY_REPLY

- 57445 (0xe065)

Key name KEY_SEARCH

- 57446 (0xe066)

Key name KEY_BOOKMARKS

- 57447 (0xe067)

Key name KEY_REFRESH

- 57448 (0xe068)

Key name KEY_STOP

- 57449 (0xe069)

Key name KEY_FORWARD

- 57450 (0xe06a)

Key name KEY_BACK

- 57451 (0xe06b)

Key name KEY_COMPUTER

- 57452 (0xe06c)

Key name KEY_MAIL

- 57453 (0xe06d)

Key name KEY_MEDIA

- 57455 (0xe06f)

Key name KEY_MACRO

- 57456 (0xe070)

Key name KEY_DOCUMENTS

- 57457 (0xe071)

Key name KEY_BATTERY

- 57458 (0xe072)

Key name KEY_BLUETOOTH

- 57459 (0xe073)

Key name KEY_WLAN

- 57460 (0xe074)

Key name KEY_UWB

- 57461 (0xe075)

Key name KEY_HELP

- 57462 (0xe076)

Key name KEY_KPLEFTPAREN

- 57463 (0xe077)

Key name KEY_F18

- 57464 (0xe078)

Key name KEY_COPY

- 57465 (0xe079)

Key name KEY_F22

- 57467 (0xe07b)

Key name KEY_KPRIGHTPAREN

- 57469 (0xe07d)

Key name KEY_EJECTCLOSECD