

NAME

virkeycode-usb – Key code values for usb

DESCRIPTION

List of usb key code values, with corresponding linux key code names

- 4 (0x4)

Key name KEY_A

- 5 (0x5)

Key name KEY_B

- 6 (0x6)

Key name KEY_C

- 7 (0x7)

Key name KEY_D

- 8 (0x8)

Key name KEY_E

- 9 (0x9)

Key name KEY_F

- 10 (0xa)

Key name KEY_G

- 11 (0xb)

Key name KEY_H

- 12 (0xc)

Key name KEY_I

- 13 (0xd)

Key name KEY_J

- 14 (0xe)

Key name KEY_K

- 15 (0xf)

Key name KEY_L

- 16 (0x10)

Key name KEY_M

- 17 (0x11)

Key name KEY_N

- 18 (0x12)

Key name KEY_O

- 19 (0x13)

Key name KEY_P

- 20 (0x14)

Key name KEY_Q

- 21 (0x15)

Key name KEY_R

- 22 (0x16)

Key name KEY_S

- 23 (0x17)

Key name KEY_T

- 24 (0x18)

Key name KEY_U

- 25 (0x19)

Key name KEY_V

- 26 (0x1a)

Key name KEY_W

- 27 (0x1b)

Key name KEY_X

- 28 (0x1c)

Key name KEY_Y

- 29 (0x1d)

Key name KEY_Z

- 30 (0x1e)

Key name KEY_1

- 31 (0x1f)

Key name KEY_2

- 32 (0x20)

Key name KEY_3

- 33 (0x21)

Key name KEY_4

- 34 (0x22)

Key name KEY_5

- 35 (0x23)

Key name KEY_6

- 36 (0x24)

Key name KEY_7

- 37 (0x25)

Key name KEY_8

- 38 (0x26)

Key name KEY_9

- 39 (0x27)

Key name KEY_0

- 40 (0x28)

Key name KEY_ENTER

- 41 (0x29)

Key name KEY_ESC

- 42 (0x2a)

Key name KEY_BACKSPACE

- 43 (0x2b)

Key name KEY_TAB

- 44 (0x2c)

Key name KEY_SPACE

- 45 (0x2d)

Key name KEY_MINUS

- 46 (0x2e)

Key name KEY_EQUAL

- 47 (0x2f)

Key name KEY_LEFTBRACE

- 48 (0x30)

Key name KEY_RIGHTBRACE

- 49 (0x31)

Key name KEY_BACKSLASH

- 50 (0x32)

Key name KEY_BACKSLASH

- 51 (0x33)

Key name KEY_SEMICOLON

- 52 (0x34)

Key name KEY_APOSTROPHE

- 53 (0x35)

Key name KEY_GRAVE

- 54 (0x36)

Key name KEY_COMMA

- 55 (0x37)

Key name KEY_DOT

- 56 (0x38)

Key name KEY_SLASH

- 57 (0x39)

Key name KEY_CAPSLOCK

- 58 (0x3a)

Key name KEY_F1

- 59 (0x3b)

Key name KEY_F2

- 60 (0x3c)

Key name KEY_F3

- 61 (0x3d)

Key name KEY_F4

- 62 (0x3e)

Key name KEY_F5

- 63 (0x3f)

Key name KEY_F6

- 64 (0x40)

Key name KEY_F7

- 65 (0x41)

Key name KEY_F8

- 66 (0x42)

Key name KEY_F9

- 67 (0x43)

Key name KEY_F10

- 68 (0x44)

Key name KEY_F11

- 69 (0x45)

Key name KEY_F12

- 70 (0x46)

Key name KEY_SYSRQ

- 71 (0x47)

Key name KEY_SCROLLLOCK

- 72 (0x48)

Key name KEY_PAUSE

- 73 (0x49)

Key name KEY_INSERT

- 74 (0x4a)

Key name KEY_HOME

- 75 (0x4b)

Key name KEY_PAGEUP

- 76 (0x4c)

Key name KEY_DELETE

- 77 (0x4d)

Key name KEY_END

- 78 (0x4e)

Key name KEY_PAGEDOWN

- 79 (0x4f)

Key name KEY_RIGHT

- 80 (0x50)

Key name KEY_LEFT

- 81 (0x51)

Key name KEY_DOWN

- 82 (0x52)

Key name KEY_UP

- 83 (0x53)

Key name KEY_NUMLOCK

- 84 (0x54)

Key name KEY_KPSLASH

- 85 (0x55)

Key name KEY_KPASTERISK

- 86 (0x56)

Key name KEY_KPMINUS

- 87 (0x57)

Key name KEY_KPPLUS

- 88 (0x58)

Key name KEY_KPENTER

- 89 (0x59)

Key name KEY_KP1

- 90 (0x5a)

Key name KEY_KP2

- 91 (0x5b)

Key name KEY_KP3

- 92 (0x5c)

Key name KEY_KP4

- 93 (0x5d)

Key name KEY_KP5

- 94 (0x5e)

Key name KEY_KP6

- 95 (0x5f)

Key name KEY_KP7

- 96 (0x60)

Key name KEY_KP8

- 97 (0x61)

Key name KEY_KP9

- 98 (0x62)

Key name KEY_KP0

- 99 (0x63)

Key name KEY_KPDOT

- 100 (0x64)

Key name KEY_102ND

- 101 (0x65)

Key name KEY_COMPOSE

- 102 (0x66)

Key name KEY_POWER

- 103 (0x67)

Key name KEY_KPEQUAL

- 104 (0x68)

Key name KEY_F13

- 105 (0x69)

Key name KEY_F14

- 106 (0x6a)

Key name KEY_F15

- 107 (0x6b)

Key name KEY_F16

- 108 (0x6c)

Key name KEY_F17

- 109 (0x6d)

Key name KEY_F18

- 110 (0x6e)

Key name KEY_F19

- 111 (0x6f)

Key name KEY_F20

- 112 (0x70)

Key name KEY_F21

- 113 (0x71)

Key name KEY_F22

- 114 (0x72)

Key name KEY_F23

- 115 (0x73)

Key name KEY_F24

- 116 (0x74)

Key name KEY_OPEN

- 117 (0x75)

Key name KEY_HELP

- 118 (0x76)

Key name KEY_MENU

- 119 (0x77)

Key name KEY_FRONT

- 120 (0x78)

Key name KEY_STOP

- 121 (0x79)

Key name KEY_AGAIN

- 122 (0x7a)

Key name KEY_UNDO

- 123 (0x7b)

Key name KEY_CUT

- 124 (0x7c)

Key name KEY_COPY

- 125 (0x7d)

Key name KEY_PASTE

- 126 (0x7e)

Key name KEY_FIND

- 127 (0x7f)

Key name KEY_MUTE

- 128 (0x80)

Key name KEY_VOLUMEUP

- 129 (0x81)

Key name KEY_VOLUMEDOWN

- 133 (0x85)

Key name KEY_KPCOMMA

- 135 (0x87)

Key name KEY_RO

- 136 (0x88)

Key name KEY_KATAKANAHIRAGANA

- 137 (0x89)

Key name KEY_YEN

- 138 (0x8a)

Key name KEY_HENKAN

- 139 (0x8b)

Key name KEY_MUHENKAN

- 140 (0x8c)

Key name KEY_KPJPCOMMA

- 144 (0x90)

Key name KEY_HANGEUL

- 145 (0x91)

Key name KEY_HANJA

- 146 (0x92)

Key name KEY_KATAKANA

- 147 (0x93)

Key name KEY_HIRAGANA

- 148 (0x94)

Key name KEY_ZENKAKUHANKAKU

- 182 (0xb6)

Key name KEY_KPLEFTPAREN

- 183 (0xb7)

Key name KEY_KPRIGHTPAREN

- 224 (0xe0)

Key name KEY_LEFTCTRL

- 225 (0xe1)

Key name KEY_LEFTSHIFT

- 226 (0xe2)

Key name KEY_LEFTALT

- 227 (0xe3)

Key name KEY_LEFTMETA

- 228 (0xe4)

Key name KEY_RIGHTCTRL

- 229 (0xe5)

Key name KEY_RIGHTSHIFT

- 230 (0xe6)

Key name KEY_RIGHTALT

- 231 (0xe7)

Key name KEY_RIGHTMETA

- 232 (0xe8)

Key name KEY_PLAYPAUSE

- 233 (0xe9)

Key name KEY_STOPCD

- 234 (0xea)

Key name KEY_PREVIOUSSONG

- 235 (0xeb)

Key name KEY_NEXTSONG

- 236 (0xec)

Key name KEY_EJECTCD

- 237 (0xed)

Key name KEY_VOLUMEUP

- 238 (0xee)

Key name KEY_VOLUMEDOWN

- 239 (0xef)

Key name KEY_MUTE

- 240 (0xf0)

Key name KEY_WWW

- 241 (0xf1)

Key name KEY_BACK

- 242 (0xf2)

Key name KEY_FORWARD

- 243 (0xf3)

Key name KEY_STOP

- 244 (0xf4)

Key name KEY_FIND

- 245 (0xf5)

Key name KEY_SCROLLUP

- 246 (0xf6)

Key name KEY_SCROLLDOWN

- 247 (0xf7)

Key name KEY_EDIT

- 248 (0xf8)

Key name KEY_SLEEP

- 249 (0xf9)

Key name KEY_SCREENLOCK

- 250 (0xfa)

Key name KEY_REFRESH

- 251 (0xfb)

Key name KEY_CALC