



Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'gslj.1'

\$ man gslj.1

GSLP(1) Ghostscript GSLP(1)

NAME

- gslp - Format and print text using ghostscript
- gsbj - Format and print text for BubbleJet printer using ghostscript
- gsdj - Format and print text for DeskJet printer using ghostscript
- gsdj500 - Format and print text for DeskJet 500 BubbleJet using ghostscript
- gslj - Format and print text for LaserJet printer using ghostscript

SYNOPSIS

- gslp -12BclqRr -b<header> -f -F<hfont> -L<lines> -p<outfile> -T<n>
- add-to-space <units> --add-to-width <units> --columns <n> --detect --first-page <n>
- kern <file.afm> --last-page <n> --(heading|footing)-(left|center|right) <string> --mar?
- gin-(top|bottom|left|right) <inches> --no-eject-(file|formfeed) --spacing <n> [gs options]
- [files]
- gsbj [options] [files]
- gsdj [options] [files]
- gsdj500 [options] [files]
- gslj [options] [files]

DESCRIPTION

This utility provides functionality approximately equivalent to the Unix `enscript(1)` program. It prints plain text files using a single font. It currently handles tabs and formfeeds, but not backspaces. It will line-wrap when using fixed-pitch fonts. It will also do kerning and width adjustment.

The default device (`-sDEVICE=`) and resolution (`-r`) are as follows:

gslp epson 180
gsbj bj10e 180
gsdj deskjet 300
gsdj500 djet500 300
gslj laserjet 300

By default the current date is formatted as the center header.

OPTIONS

Standard switches implemented:

-12BclqRr -b<header> -f -F<hfont> -L<lines> -p<outfile>

Sun switches implemented:

-T<n> set tab width

Switches ignored:

-GghKkmow -# -C -d -J -n -P -S -s -t -v

Switches added:

--add-to-space <units>

add the given number of 1/72" units to the width of each space (may be negative)

--add-to-width <units>

add the given number of 1/72" units to the width of each character (may be negative)

--columns <n>

print in <n> columns

--detect

treat the file as PostScript if it starts with %!

--first-page <n>

start printing at page <n>

--kern <file.afm>

kern using information from the given .AFM file

--last-page <n>

stop printing after page <n>

--(heading|footing)-(left|center|right) <string>

set the heading/footing fields; use -B first to clear

--margin-(top|bottom|left|right) <inches>

set a margin

--no-eject-(file|formfeed)

end-of-file/FF only starts a new column, not a new sheet

--spacing <n>

use double (n=2), triple (n=3), etc. spacing

Also, the string %# in a heading or footing is replaced with the page #.

SEE ALSO

gs(1)

VERSION

This document was last revised for Ghostscript version 9.55.0.

AUTHOR

Artifex Software, Inc. are the primary maintainers of Ghostscript. This manpage by George Ferguson.

9.55.0

27 September 2021

GSLP(1)