



Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'vgimport.8'

\$ man vgimport.8

VGIMPORT(8) System Manager's Manual VGIMPORT(8)

NAME

vgimport - Register exported volume group with system

SYNOPSIS

vgimport option_args position_args
[option_args]

DESCRIPTION

vgimport makes exported VGs known to the system again, perhaps after moving the PVs from a different system.

vgexport clears the VG system ID, and vgimport sets the VG system ID to match the host running vgimport (if the host has a system ID).

USAGE

Import specified VGs.

vgimport VG|Tag|Select ...

[-S|--select String]

[COMMON_OPTIONS]

Import all VGs.

vgimport -a|--all

[COMMON_OPTIONS]

Common options for command:

[-f|--force]

[--reportformat basic|json]

Common options for lvm:

[-d|--debug]
[-h|--help]
[-q|--quiet]
[-t|--test]
[-v|--verbose]
[-y|--yes]
[--commandprofile String]
[--config String]
[--driverloaded y|n]
[--lockopt String]
[--longhelp]
[--nolocking]
[--profile String]
[--version]

OPTIONS

-a|--all

Import all visible VGs.

--commandprofile String

The command profile to use for command configuration. See `lvm.conf(5)` for more information about profiles.

--config String

Config settings for the command. These override `lvm.conf` settings. The String arg uses the same format as `lvm.conf`, or may use section/field syntax. See `lvm.conf(5)` for more information about config.

-d|--debug ...

Set debug level. Repeat from 1 to 6 times to increase the detail of messages sent to the log file and/or syslog (if configured).

--driverloaded y|n

If set to no, the command will not attempt to use device-mapper. For testing and debugging.

-f|--force ...

Override various checks, confirmations and protections. Use with extreme caution.

-h|--help

Display help text.

`--lockopt` String

Used to pass options for special cases to `lvmlckd`. See `lvmlckd(8)` for more information.

`--longhelp`

Display long help text.

`--nolocking`

Disable locking.

`--profile` String

An alias for `--commandprofile` or `--metadataprofile`, depending on the command.

`-q|--quiet` ...

Suppress output and log messages. Overrides `--debug` and `--verbose`. Repeat once to also suppress any prompts with answer 'no'.

`--reportformat` basic|json

Overrides current output format for reports which is defined globally by the `report/output_format` setting in `lvm.conf`. `basic` is the original format with columns and rows. If there is more than one report per command, each report is prefixed with the report name for identification. `json` produces report output in JSON format. See `lvmreport(7)` for more information.

`-S|--select` String

Select objects for processing and reporting based on specified criteria. The criteria syntax is described by `--select help` and `lvmreport(7)`. For reporting commands, one row is displayed for each object matching the criteria. See `--options help` for selectable object fields. Rows can be displayed with an additional "selected" field (`-o selected`) showing 1 if the row matches the selection and 0 otherwise. For non-reporting commands which process LVM entities, the selection is used to choose items to process.

`-t|--test`

Run in test mode. Commands will not update metadata. This is implemented by disabling all metadata writing but nevertheless returning success to the calling function. This may lead to unusual error messages in multi-stage operations if a tool relies on reading back metadata it believes has changed but hasn't.

`-v|--verbose` ...

Set verbose level. Repeat from 1 to 4 times to increase the detail of messages sent to stdout and stderr.

--version

Display version information.

-y|--yes

Do not prompt for confirmation interactively but always assume the answer yes. Use with extreme caution. (For automatic no, see -qq.)

VARIABLES

VG

Volume Group name. See `lvm(8)` for valid names.

Tag

Tag name. See `lvm(8)` for information about tag names and using tags in place of a VG, LV or PV.

Select

Select indicates that a required positional parameter can be omitted if the `--select` option is used. No arg appears in this position.

String

See the option description for information about the string content.

Size[UNIT]

Size is an input number that accepts an optional unit. Input units are always treated as base two values, regardless of capitalization, e.g. 'k' and 'K' both refer to 1024. The default input unit is specified by letter, followed by |UNIT.

UNIT represents other possible input units: bBsSkKmMgGtTpPeE. b|B is bytes, s|S is sectors of 512 bytes, k|K is KiB, m|M is MiB, g|G is GiB, t|T is TiB, p|P is PiB, e|E is EiB. (This should not be confused with the output control `--units`, where capital letters mean multiple of 1000.)

ENVIRONMENT VARIABLES

See `lvm(8)` for information about environment variables used by `lvm`. For example, `LVM_VG_NAME` can generally be substituted for a required VG parameter.

SEE ALSO

`lvm(8)` `lvm.conf(5)` `lvmconfig(8)`

`pvchange(8)` `pvck(8)` `pvcreate(8)` `pvdisplay(8)` `pvmove(8)` `pvremove(8)` `pvresize(8)` `pvs(8)` `pvs?`

`can(8)`

vgcfgbackup(8) vgcfgrestore(8) vgchange(8) vgck(8) vgcreate(8) vgconvert(8) vgdisplay(8)
vgexport(8) vgextend(8) vgimport(8) vgimportclone(8) vgmerge(8) vgmknodes(8) vgreduce(8)
vgremove(8) vgrename(8) vgs(8) vgscan(8) vgsplit(8)
lvcreate(8) lvchange(8) lvconvert(8) lvdisplay(8) lvextend(8) lvreduce(8) lvremove(8)
lvrename(8) lvresize(8) lvs(8) lvscan(8)
lvm-fullreport(8) lvm-lvpoll(8) lvm2-activation-generator(8) blkdeactivate(8) lvmdump(8)
dmeventd(8) lvmpolld(8) lvmlockd(8) lvmlockctl(8) cmirror(8) lvmdbusd(8)
lvmsystemid(7) lvmreport(7) lvmraid(7) lvmthin(7) lvmcache(7)

Red Hat, Inc.

LVM TOOLS 2.03.11(2) (2021-01-08)

VGIMPORT(8)