



python



PowerShell

FPDF Library
PDF generator

Full credit is given to the above companies including the OS that this PDF file was generated!

PowerShell Get-Help on command 'Disable-NetDnsTransitionConfiguration'

PS C:\Users\wahid> Get-Help Disable-NetDnsTransitionConfiguration

NAME

Disable-NetDnsTransitionConfiguration

SYNOPSIS

Disables the DNS64 configuration on a computer.

SYNTAX

Disable-NetDnsTransitionConfiguration [-Adapter <CimInstance>] [-AsJob]
[-CimSession <CimSession[]>] [-Confirm] [-PassThru] [-ThrottleLimit <Int32>]
[-WhatIf] [<CommonParameters>]

Disable-NetDnsTransitionConfiguration [-AsJob] [-CimSession <CimSession[]>]
[-Confirm] -InputObject <CimInstance[]> [-PassThru] [-ThrottleLimit <Int32>]
[-WhatIf] [<CommonParameters>]

DESCRIPTION

The Disable-NetDnsTransitionConfiguration makes the DNS64 configuration ineffective on a computer.

PARAMETERS

-Adapter <CimInstance>

Specifies the network adapter on which to disable the DNS64.

-AsJob [<SwitchParameter>]

Runs the cmdlet as a background job. Use this parameter to run commands that take a long time to complete.

-CimSession <CimSession[]>

Runs the cmdlet in a remote session or on a remote computer. Enter a computer name or a session object, such as the output of a `New-CimSession` (<https://go.microsoft.com/fwlink/p/?LinkId=227967>) or `[Get-CimSession](https://go.microsoft.com/fwlink/p/?LinkId=227966)cmdlet`. The default is the current session on the local computer.

-Confirm [<SwitchParameter>]

Prompts you for confirmation before running the cmdlet.

-InputObject <CimInstance[]>

Specifies the input object that is used in a pipeline command.

-PassThru [<SwitchParameter>]

Returns an object representing the item with which you are working. By default, this cmdlet does not generate any output.

-ThrottleLimit <Int32>

Specifies the maximum number of concurrent operations that can be established to run the cmdlet. If this parameter is omitted or a value of `0` is entered, then Windows PowerShell calculates an optimum throttle limit for the cmdlet based on the number of CIM cmdlets that are running on the computer. The throttle limit applies only to the current cmdlet, not to the session or to the computer.

-WhatIf [<SwitchParameter>]

Shows what would happen if the cmdlet runs. The cmdlet is not run.

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

----- Example 1: Disable the DNS64 configuration -----

```
PS C:\>Disable-NetDnsTransitionConfiguration
```

This command makes the DNS64 configuration ineffective.

REMARKS

To see the examples, type: "get-help Disable-NetDnsTransitionConfiguration -examples".

For more information, type: "get-help Disable-NetDnsTransitionConfiguration -detailed".

For technical information, type: "get-help Disable-NetDnsTransitionConfiguration -full".

For online help, type: "get-help Disable-NetDnsTransitionConfiguration -online"