



python



PowerShell

FPDF Library
PDF generator

Full credit is given to the above companies including the OS that this PDF file was generated!

PowerShell Get-Help on command 'Enable-RunspaceDebug'

PS C:\Users\wahid> Get-Help Enable-RunspaceDebug

NAME

Enable-RunspaceDebug

SYNOPSIS

Enables debugging on runspaces where any breakpoint is preserved until a debugger is attached.

SYNTAX

```
Enable-RunspaceDebug [[-ProcessName] <System.String>] [[-AppDomainName] <System.String[]>] [<CommonParameters>]
```

```
Enable-RunspaceDebug [[-RunspaceName] <System.String[]>] [[-BreakAll]] [<CommonParameters>]
```

```
Enable-RunspaceDebug [-Runspace] <System.Management.Automation.Runspaces.Runspace[]> [[-BreakAll]] [<CommonParameters>]
```

```
Enable-RunspaceDebug [-RunspaceId] <System.Int32[]> [[-BreakAll]] [<CommonParameters>]
```

Enable-RunspaceDebug [-RunspaceInstanceId] <System.Guid[]> [<CommonParameters>]

DESCRIPTION

The `Enable-RunspaceDebug` cmdlet enables debugging on runspaces where any breakpoint is preserved until a debugger is attached.

PARAMETERS

-AppDomainName <System.String[]>

The name of the application domain that hosts the PowerShell runspace.

-BreakAll <System.Management.Automation.SwitchParameter>

Causes any running command or script in the Runspace to stop in step mode, regardless of whether a debugger is currently attached. The script or command will remain stopped until a debugger is attached to debug the current stop point.

-ProcessName <System.String>

The name of the process that hosts the PowerShell runspace.

-Runspace <System.Management.Automation.Runspaces.Runspace[]>

One or more Runspace objects to be disabled.

-RunspaceId <System.Int32[]>

One or more Runspace Id numbers to be disabled.

-RunspaceInstanceId <System.Guid[]>

One or more Runspace GUIDs to be disabled.

-RunspaceName <System.String[]>

One or more Runspace names to be disabled.

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

----- 1: Enable the default runspace debugger -----

Enable-RunspaceDebug

Get-RunspaceDebug

Id Name	Enabled	BreakAll
-----	-----	-----
1 Runspace1	True	False

REMARKS

To see the examples, type: "get-help Enable-RunspaceDebug -examples".

For more information, type: "get-help Enable-RunspaceDebug -detailed".

For technical information, type: "get-help Enable-RunspaceDebug -full".

For online help, type: "get-help Enable-RunspaceDebug -online"