



python



PowerShell

FPDF Library
PDF generator

Full credit is given to the above companies including the OS that this PDF file was generated!

PowerShell Get-Help on command 'Set-DtcDefault'

PS C:\Users\wahid> Get-Help Set-DtcDefault

NAME

Set-DtcDefault

SYNOPSIS

Sets the default transactions coordinator.

SYNTAX

```
Set-DtcDefault [-AsJob] [-CimSession <CimSession[]>] [-ServerName <String>]  
[-ThrottleLimit <Int32>] [<CommonParameters>]
```

DESCRIPTION

The Set-DtcDefault cmdlet sets the default transactions coordinator.

PARAMETERS

-AsJob [<SwitchParameter>]

Runs the cmdlet as a background job. Use this parameter to run commands that take a long time to complete.

The cmdlet immediately returns an object that represents the job and then displays the command prompt. You can continue to work in the session while the job completes. To manage the job, use the `*-Job` cmdlets. To get the job results, use the Receive-Job
(<https://go.microsoft.com/fwlink/?LinkID=113372>) cmdlet.

For more information about Windows PowerShell background jobs, see about_Jobs (<https://go.microsoft.com/fwlink/?LinkID=113251>).

-CimSession <CimSession[]>

Runs the cmdlet in a remote session or on a remote computer. Enter a computer name or a session object, such as the output of a New-CimSession
(<https://go.microsoft.com/fwlink/p/?LinkId=227967>) or [Get-CimSession] (<https://go.microsoft.com/fwlink/p/?LinkId=227966>) cmdlet.
The default is the current session on the local computer.

-ServerName <String>

Specifies the host name or virtual server name of the Distributed Transaction Coordinator (DTC) to set as the default coordinator. If you do not specify this parameter, this cmdlet specifies the local DTC as the default coordinator.

-ThrottleLimit <Int32>

Specifies the maximum number of concurrent operations that can be established to run the cmdlet. If this parameter is omitted or a value of `0` is entered, then Windows PowerShell calculates an optimum throttle limit for the cmdlet based on the number of CIM cmdlets that are running on the computer. The throttle limit applies only to the current cmdlet, not to the session or to the computer.

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable,

`OutBuffer`, `PipelineVariable`, and `OutVariable`. For more information, see [about_CommonParameters](#) (<https://go.microsoft.com/fwlink/?LinkID=113216>).

----- Example 1: Set the default DTC coordinator -----

```
PS C:\> Set-DtcDefault -ServerName "host14"
```

This command sets the default DTC coordinator to host14.

REMARKS

To see the examples, type: "get-help Set-DtcDefault -examples".

For more information, type: "get-help Set-DtcDefault -detailed".

For technical information, type: "get-help Set-DtcDefault -full".

For online help, type: "get-help Set-DtcDefault -online"