



python



PowerShell

FPDF Library
PDF generator

Full credit is given to the above companies including the OS that this PDF file was generated!

PowerShell Get-Help on command 'Set-DtcTransactionsTraceSession'

PS C:\Users\wahid> Get-Help Set-DtcTransactionsTraceSession

NAME

Set-DtcTransactionsTraceSession

SYNOPSIS

Modifies the DTC transactions trace setting of the host.

SYNTAX

```
Set-DtcTransactionsTraceSession [-AsJob] -BufferCount <UInt32> [-CimSession  
<CimSession[]>] [-ThrottleLimit <Int32>] [<CommonParameters>]
```

DESCRIPTION

The Set-DtcTransactionsTraceSession cmdlet modifies the Distributed Transaction Coordinator (DTC) transactions trace setting of the host.

PARAMETERS

-AsJob [<SwitchParameter>]

Runs the cmdlet as a background job. Use this parameter to run commands that take a long time to complete.

The cmdlet immediately returns an object that represents the job and then displays the command prompt. You can continue to work in the session while the job completes. To manage the job, use the `*-Job` cmdlets. To get the job results, use the Receive-Job
(<https://go.microsoft.com/fwlink/?LinkId=113372>) cmdlet.

For more information about Windows PowerShell background jobs, see about_Jobs (<https://go.microsoft.com/fwlink/?LinkId=113251>).

-BufferCount <UInt32>

Specifies the number of buffers to use for a DTC transactions trace.

-CimSession <CimSession[]>

Runs the cmdlet in a remote session or on a remote computer. Enter a computer name or a session object, such as the output of a New-CimSession
(<https://go.microsoft.com/fwlink/p/?LinkId=227967>) or [Get-CimSession] (<https://go.microsoft.com/fwlink/p/?LinkId=227966>) cmdlet.

The default is the current session on the local computer.

-ThrottleLimit <Int32>

Specifies the maximum number of concurrent operations that can be established to run the cmdlet. If this parameter is omitted or a value of `0` is entered, then Windows PowerShell® calculates an optimum throttle limit for the cmdlet based on the number of CIM cmdlets that are running on the computer. The throttle limit applies only to the current cmdlet, not to the session or to the computer.

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkId=113216>).

-- Example 1: Set the transactions trace session buffer count --

```
PS C:\> Set-DtcTransactionsTraceSession -BufferCount 32
```

This command sets the DTC transactions trace session buffer count to 32.

REMARKS

To see the examples, type: "get-help Set-DtcTransactionsTraceSession -examples".

For more information, type: "get-help Set-DtcTransactionsTraceSession -detailed".

For technical information, type: "get-help Set-DtcTransactionsTraceSession -full".

For online help, type: "get-help Set-DtcTransactionsTraceSession -online"