



*Full credit is given to the above companies including the OS that this PDF file was generated!*

### ***Rocky Enterprise Linux 9.2 Manual Pages on command 'adjtime\_config.5'***

***\$ man adjtime\_config.5***

ADJTIME\_CONFIG(5) File formats ADJTIME\_CONFIG(5)

#### NAME

adjtime\_config - information about hardware clock setting and drift factor

#### SYNOPSIS

/etc/adjtime

#### DESCRIPTION

The file /etc/adjtime contains descriptive information about the hardware mode clock setting and clock drift factor. The file is read and write by hwclock(8); and read by programs like rtcwake to get RTC time mode.

The file is usually located in /etc, but tools like hwclock(8) or rtcwake(8) can use alternative location by command line options if write access to /etc is unwanted. The default clock mode is "UTC" if the file is missing.

The Hardware Clock is usually not very accurate. However, much of its inaccuracy is completely predictable - it gains or loses the same amount of time every day. This is called systematic drift. The util

hwclock(8) keeps the file /etc/adjtime, that keeps some historical information. For more details see "The Adjust Function" and "The Adjtime File" sections from hwclock(8) man page.

The format of the adjtime file is, in ASCII.

#### First line

Three numbers, separated by blanks:

drift factor

the systematic drift rate in seconds per day (floating point decimal)

last adjust time

the resulting number of seconds since 1969 UTC of most recent adjustment or calibration (decimal integer)

adjustment status

zero (for compatibility with clock(8)) as a floating point decimal

#### Second line

last calibration time

The resulting number of seconds since 1969 UTC of most recent calibration. Zero if there has been no calibration yet or it is known that any previous calibration is moot (for example, because the Hardware Clock has been found, since that calibration, not to contain a valid time). This is a decimal integer.

#### Third line

clock mode

Supported values are UTC or LOCAL. Tells whether the Hardware Clock is set to Coordinated Universal Time or local time. You can always override this value with options on the hwclock(8) command line.

#### FILES

/etc/adjtime

#### SEE ALSO

hwclock(8), rtcwake(8)

#### REPORTING BUGS

For bug reports, use the issue tracker at

<https://github.com/karelzak/util-linux/issues>.

## AVAILABILITY

adjtime\_config is part of the util-linux package which can be downloaded from Linux Kernel Archive <<https://www.kernel.org/pub/linux/utils/util-linux/>>.

util-linux 2.37.4            2022-02-14            ADJTIME\_CONFIG(5)