



*Full credit is given to the above companies including the OS that this PDF file was generated!*

### ***Rocky Enterprise Linux 9.2 Manual Pages on command 'blockdev.8'***

**\$ man blockdev.8**

BLOCKDEV(8)                      System Administration                      BLOCKDEV(8)

#### NAME

blockdev - call block device ioctls from the command line

#### SYNOPSIS

blockdev [-q] [-v] command [command...] device [device...]

blockdev --report [device...]

blockdev -h|-V

#### DESCRIPTION

The utility blockdev allows one to call block device ioctls from the command line.

#### OPTIONS

-q

Be quiet.

-v

Be verbose.

--report

Print a report for the specified device. It is possible to give multiple devices. If none is given, all devices which appear in

/proc/partitions are shown. Note that the partition StartSec is in 512-byte sectors.

-h, --help

Display help text and exit.

-V, --version

Print version and exit.

## COMMANDS

It is possible to give multiple devices and multiple commands.

--flushbufs

Flush buffers.

--getalignoff

Get alignment offset.

--getbsz

Print the blocksize in bytes. This size does not describe device topology. It's the size used internally by the kernel and it may be modified (for example) by filesystem driver on mount.

--getdiscardzeroes

Get discard zeroes support status.

--getfra

Get filesystem readahead in 512-byte sectors.

--getiomin

Get minimum I/O size.

--getioopt

Get optimal I/O size.

--getmaxsect

Get max sectors per request.

--getpbsz

Get physical block (sector) size.

--getra

Print readahead (in 512-byte sectors).

--getro

Get read-only. Print 1 if the device is read-only, 0 otherwise.

--getsize64

Print device size in bytes.

`--getsize`

Print device size (32-bit!) in sectors. Deprecated in favor of the `--getsz` option.

`--getss`

Print logical sector size in bytes - usually 512.

`--getsz`

Get size in 512-byte sectors.

`--rereadpt`

Reread partition table

`--setbsz bytes`

Set blocksize. Note that the block size is specific to the current file descriptor opening the block device, so the change of block size only persists for as long as `blockdev` has the device open, and is lost once `blockdev` exits.

`--setfra sectors`

Set filesystem readahead (same as `--setra` on 2.6 kernels).

`--setra sectors`

Set readahead (in 512-byte sectors).

`--setro`

Set read-only. The currently active access to the device may not be affected by the change. For example, a filesystem already mounted in read-write mode will not be affected. The change applies after remount.

`--setrw`

Set read-write.

## AUTHORS

`blockdev` was written by Andries E. Brouwer and rewritten by Karel Zak.

## REPORTING BUGS

For bug reports, use the issue tracker at <https://github.com/karelzak/util-linux/issues>.

## AVAILABILITY

The `blockdev` command is part of the `util-linux` package which can be

downloaded from Linux Kernel Archive

<<https://www.kernel.org/pub/linux/utils/util-linux/>>.

util-linux 2.37.4

2022-02-14

BLOCKDEV(8)