

Full credit is given to the above companies including the OS that this PDF file was generated!

# Rocky Enterprise Linux 9.2 Manual Pages on command 'mv.1'

## \$ man mv.1

MV(1)

**User Commands** 

MV(1)

NAME

mv - move (rename) files

#### **SYNOPSIS**

mv [OPTION]... [-T] SOURCE DEST

mv [OPTION]... SOURCE... DIRECTORY

mv [OPTION]... -t DIRECTORY SOURCE...

### **DESCRIPTION**

Rename SOURCE to DEST, or move SOURCE(s) to DIRECTORY.

Mandatory arguments to long options are mandatory for short options

too.

## --backup[=CONTROL]

make a backup of each existing destination file

- -b like --backup but does not accept an argument
- -f, --force

do not prompt before overwriting

-i, --interactive

prompt before overwrite Page 1/3

```
-n, --no-clobber
    do not overwrite an existing file
If you specify more than one of -i, -f, -n, only the final one takes
effect.
--strip-trailing-slashes
    remove any trailing slashes from each SOURCE argument
-S, --suffix=SUFFIX
    override the usual backup suffix
-t, --target-directory=DIRECTORY
    move all SOURCE arguments into DIRECTORY
-T, --no-target-directory
    treat DEST as a normal file
-u, --update
    move only when the SOURCE file is newer than the destination
    file or when the destination file is missing
-v, --verbose
    explain what is being done
-Z, --context
    set SELinux security context of destination file to default type
--help display this help and exit
--version
    output version information and exit
The backup suffix is '~', unless set with --suffix or SIM?
PLE_BACKUP_SUFFIX. The version control method may be selected via the
--backup option or through the VERSION_CONTROL environment variable.
Here are the values:
none, off
    never make backups (even if --backup is given)
numbered, t
    make numbered backups
existing, nil
    numbered if numbered backups exist, simple otherwise
```

simple, never

Page 2/3

always make simple backups

### **AUTHOR**

Written by Mike Parker, David MacKenzie, and Jim Meyering.

### **REPORTING BUGS**

GNU coreutils online help: <a href="https://www.gnu.org/software/coreutils/">https://www.gnu.org/software/coreutils/</a>

Report any translation bugs to <a href="https://translationproject.org/team/">https://translationproject.org/team/</a>

### **COPYRIGHT**

Copyright ? 2020 Free Software Foundation, Inc. License GPLv3+: GNU

GPL version 3 or later <a href="https://gnu.org/licenses/gpl.html">https://gnu.org/licenses/gpl.html</a>.

This is free software: you are free to change and redistribute it.

There is NO WARRANTY, to the extent permitted by law.

### SEE ALSO

rename(2)

Full documentation <a href="https://www.gnu.org/software/coreutils/mv">https://www.gnu.org/software/coreutils/mv</a>

or available locally via: info '(coreutils) mv invocation'

GNU coreutils 8.32 January 2023 MV(1)