



*Full credit is given to the above companies including the OS that this PDF file was generated!*

### ***Rocky Enterprise Linux 9.2 Manual Pages on command 'ostree-static-delta.1'***

#### ***\$ man ostree-static-delta.1***

OSTREE STATIC-DELTA(1)    ostree static-delta    OSTREE STATIC-DELTA(1)

#### NAME

ostree-static-delta - Manage static delta files

#### SYNOPSIS

ostree static-delta list  
ostree static-delta show  
ostree static-delta delete  
ostree static-delta generate [--to=REV] [OPTIONS...]  
ostree static-delta apply-offline [OPTIONS...] {PATH} [KEY-ID...]  
ostree static-delta verify [OPTIONS...] {STATIC-DELTA} [KEY-ID...]

#### DESCRIPTION

List and manipulate static delta files.

#### GENERATE OPTIONS

--from="REV"

Create delta from revision REV.

--to="REV"

Create delta to revision REV. (This option is required.) The delta is from the parent of REV, unless specified otherwise by --from or

--empty.

--empty

Create delta from scratch.

--max-usize=SIZE

Maximum uncompressed size in megabytes.

--sign-type=ENGINE

Use particular signature engine. Currently available ed25519 and dummy signature types. The default is ed25519.

--sign="KEY-ID"

There KEY-ID is:

for ed25519:

base64-encoded secret key for signing.

for dummy:

ASCII-string used as secret key.

#### APPLY-OFFLINE OPTIONS

KEY-ID

for ed25519:

base64-encoded public key for verifying.

for dummy:

ASCII-string used as public key.

--sign-type=ENGINE

Use particular signature engine. Currently available ed25519 and dummy signature types.

--keys-file

Read key(s) from file filename. Valid for ed25519 signature type.

For ed25519 this file must contain base64-encoded public key(s) per line for verifying.

--keys-dir

Redefine the system path, where to search files and subdirectories with well-known and revoked keys.

#### VERIFY OPTIONS

KEY-ID

for ed25519:

base64-encoded public key for verifying.

for dummy:

ASCII-string used as public key.

--sign-type=ENGINE

Use particular signature engine. Currently available ed25519 and dummy signature types. The default is ed25519.

--keys-file

Read key(s) from file filename. Valid for ed25519 signature type.

For ed25519 this file must contain base64-encoded public key(s) per line for verifying.

--keys-dir

Redefine the system path, where to search files and subdirectories with well-known and revoked keys.

#### EXAMPLE

```
$ ostree static-delta
```

```
(No static deltas)
```

```
OSTree
```

```
OSTREE STATIC-DELTA(1)
```