



Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'shutdown.8'

\$ man shutdown.8

SHUTDOWN(8) shutdown SHUTDOWN(8)

NAME

shutdown - Halt, power off or reboot the machine

SYNOPSIS

shutdown [OPTIONS...] [TIME] [WALL...]

DESCRIPTION

shutdown may be used to halt, power off, or reboot the machine.

The first argument may be a time string (which is usually "now").

Optionally, this may be followed by a wall message to be sent to all logged-in users before going down.

The time string may either be in the format "hh:mm" for hour/minutes specifying the time to execute the shutdown at, specified in 24h clock format. Alternatively it may be in the syntax "+m" referring to the specified number of minutes m from now. "now" is an alias for "+0", i.e. for triggering an immediate shutdown. If no time argument is specified, "+1" is implied.

Note that to specify a wall message you must specify a time argument, too.

If the time argument is used, 5 minutes before the system goes down the /run/nologin file is created to ensure that further logins shall not be allowed.

OPTIONS

The following options are understood:

--help

Print a short help text and exit.

-H, --halt

Halt the machine.

-P, --poweroff

Power the machine off (the default).

-r, --reboot

Reboot the machine.

-h

The same as --poweroff, but does not override the action to take if it is "halt". E.g. shutdown --reboot -h means "poweroff", but shutdown --halt -h means "halt".

-k

Do not halt, power off, or reboot, but just write the wall message.

--no-wall

Do not send wall message before halt, power off, or reboot.

-c

Cancel a pending shutdown. This may be used to cancel the effect of an invocation of shutdown with a time argument that is not "+0" or "now".

--show

Show a pending shutdown action and time if there is any.

EXIT STATUS

On success, 0 is returned, a non-zero failure code otherwise.

COMPATIBILITY

The

shutdown command in previous init systems (including sysvinit) defaulted to single-user mode instead of powering off the machine. To

change into single-user mode, use `systemctl rescue` instead.

SEE ALSO

`systemd(1)`, `systemctl(1)`, `halt(8)`, `wall(1)`

`systemd` 252

`SHUTDOWN(8)`