

NAME

virkeycode-win32 – Key code values for win32

DESCRIPTION

List of win32 key code values, with corresponding win32 key code names

- 1 (0x1)

Key name VK_LBUTTON

- 2 (0x2)

Key name VK_RBUTTON

- 4 (0x4)

Key name VK_MBUTTON

- 5 (0x5)

Key name VK_XBUTTON1

- 6 (0x6)

Key name VK_XBUTTON2

- 8 (0x8)

Key name VK_BACK

- 9 (0x9)

Key name VK_TAB

- 13 (0xd)

Key name VK_RETURN

- 16 (0x10)

Key name VK_LSHIFT

- 17 (0x11)

Key name VK_CONTROL

- 18 (0x12)

Key name VK_MENU

- 19 (0x13)

Key name VK_PAUSE

- 20 (0x14)

Key name VK_CAPITAL

- 21 (0x15)

Key name VK_HANGEUL

- 25 (0x19)

Key name VK_HANJA

- 27 (0x1b)

Key name VK_ESCAPE

- 32 (0x20)

Key name VK_SPACE

- 33 (0x21)

Key name VK_PRIOR

- 34 (0x22)

Key name VK_NEXT

- 35 (0x23)

Key name VK_END

- 36 (0x24)

Key name VK_HOME

- 37 (0x25)

Key name VK_LEFT

- 38 (0x26)

Key name VK_UP

- 39 (0x27)

Key name VK_RIGHT

- 40 (0x28)

Key name VK_DOWN

- 41 (0x29)

Key name VK_SELECT

- 42 (0x2a)

Key name VK_PRINT

- 44 (0x2c)

Key name VK_SNAPSHOT

- 45 (0x2d)

Key name VK_INSERT

- 46 (0x2e)

Key name VK_DELETE

- 47 (0x2f)

Key name VK_HELP

- 48 (0x30)

Key name VK_0

- 49 (0x31)

Key name VK_1

- 50 (0x32)

Key name VK_2

- 51 (0x33)

Key name VK_3

- 52 (0x34)

Key name VK_4

- 53 (0x35)

Key name VK_5

- 54 (0x36)

Key name VK_6

- 55 (0x37)

Key name VK_7

- 56 (0x38)

Key name VK_8

- 57 (0x39)

Key name VK_9

- 65 (0x41)

Key name VK_A

- 66 (0x42)

Key name VK_B

- 67 (0x43)

Key name VK_C

- 68 (0x44)

Key name VK_D

- 69 (0x45)

Key name VK_E

- 70 (0x46)

Key name VK_F

- 71 (0x47)

Key name VK_G

- 72 (0x48)

Key name VK_H

- 73 (0x49)

Key name VK_I

- 74 (0x4a)

Key name VK_J

- 75 (0x4b)

Key name VK_K

- 76 (0x4c)

Key name VK_L

- 77 (0x4d)

Key name VK_M

- 78 (0x4e)

Key name VK_N

- 79 (0x4f)

Key name VK_O

- 80 (0x50)

Key name VK_P

- 81 (0x51)

Key name VK_Q

- 82 (0x52)

Key name VK_R

- 83 (0x53)

Key name VK_S

- 84 (0x54)

Key name VK_T

- 85 (0x55)

Key name VK_U

- 86 (0x56)

Key name VK_V

- 87 (0x57)

Key name VK_W

- 88 (0x58)

Key name VK_X

- 89 (0x59)

Key name VK_Y

- 90 (0x5a)

Key name VK_Z

- 91 (0x5b)

Key name VK_LWIN

- 92 (0x5c)

Key name VK_RWIN

- 93 (0x5d)

Key name VK_APPS

- 95 (0x5f)

Key name VK_SLEEP

- 96 (0x60)

Key name VK_NUMPAD0

- 97 (0x61)

Key name VK_NUMPAD1

- 98 (0x62)

Key name VK_NUMPAD2

- 99 (0x63)

Key name VK_NUMPAD3

- 100 (0x64)

Key name VK_NUMPAD4

- 101 (0x65)

Key name VK_NUMPAD5

- 102 (0x66)

Key name VK_NUMPAD6

- 103 (0x67)

Key name VK_NUMPAD7

- 104 (0x68)

Key name VK_NUMPAD8

- 105 (0x69)

Key name VK_NUMPAD9

- 106 (0x6a)

Key name VK_MULTIPLY

- 107 (0x6b)

Key name VK_ADD

- 108 (0x6c)

Key name VK_SEPARATOR??

- 109 (0x6d)

Key name VK_SUBTRACT

- 110 (0x6e)

Key name VK_DECIMAL

- 111 (0x6f)

Key name VK_DIVIDE

- 112 (0x70)

Key name VK_F1

- 113 (0x71)

Key name VK_F2

- 114 (0x72)

Key name VK_F3

- 115 (0x73)

Key name VK_F4

- 116 (0x74)

Key name VK_F5

- 117 (0x75)

Key name VK_F6

- 118 (0x76)

Key name VK_F7

- 119 (0x77)

Key name VK_F8

- 120 (0x78)

Key name VK_F9

- 121 (0x79)

Key name VK_F10

- 122 (0x7a)

Key name VK_F11

- 123 (0x7b)

Key name VK_F12

- 124 (0x7c)

Key name VK_F13

- 125 (0x7d)

Key name VK_F14

- 126 (0x7e)

Key name VK_F15

- 127 (0x7f)

Key name VK_F16

- 128 (0x80)

Key name VK_F17

- 129 (0x81)

Key name VK_F18

- 130 (0x82)

Key name VK_F19

- 131 (0x83)

Key name VK_F20

- 132 (0x84)

Key name VK_F21

- 133 (0x85)

Key name VK_F22

- 134 (0x86)

Key name VK_F23

- 135 (0x87)

Key name VK_F24

- 144 (0x90)

Key name VK_NUMLOCK

- 145 (0x91)

Key name VK_SCROLL

- 160 (0xa0)

Key name VK_LSHIFT

- 161 (0xa1)

Key name VK_RSHIFT

- 162 (0xa2)

Key name VK_CONTROL

- 163 (0xa3)

Key name VK_RCONTROL

- 164 (0xa4)

Key name VK_MENU

- 165 (0xa5)

Key name VK_RMENU

- 166 (0xa6)

Key name VK_BROWSER_BACK

- 167 (0xa7)

Key name VK_BROWSER_FORWARD

- 168 (0xa8)

Key name VK_BROWSER_REFRESH

- 169 (0xa9)

Key name VK_BROWSER_STOP

- 170 (0xaa)

Key name VK_BROWSER_SEARCH

- 171 (0xab)

Key name VK_BROWSER_FAVOURITES

- 172 (0xac)

Key name VK_BROWSER_HOME

- 173 (0xad)

Key name VK_VOLUME_MUTE

- 174 (0xae)

Key name VK_VOLUME_DOWN

- 175 (0xaf)

Key name VK_VOLUME_UP

- 176 (0xb0)

Key name VK_MEDIA_NEXT_TRACK

- 177 (0xb1)

Key name VK_MEDIA_PREV_TRACK

- 178 (0xb2)

Key name VK_MEDIA_STOP

- 179 (0xb3)

Key name VK_MEDIA_PLAY_PAUSE

- 180 (0xb4)

Key name VK_LAUNCH_MAIL

- 186 (0xba)

Key name VK_OEM_1

- 187 (0xbb)

Key name VK_OEM_PLUS

- 188 (0xbc)

Key name VK_OEM_COMMA

- 189 (0xbd)

Key name VK_OEM_MINUS

- 190 (0xbe)

Key name VK_OEM_PERIOD

- 191 (0xbf)

Key name VK_OEM_2

- 192 (0xc0)

Key name VK_OEM_3

- 219 (0xdb)

Key name VK_OEM_4

- 220 (0xdc)

Key name VK_OEM_5

- 221 (0xdd)

Key name VK_OEM_6

- 222 (0xde)

Key name VK_OEM_7

- 225 (0xe1)

Key name VK_OEM_102

- 250 (0xfa)

Key name VK_PLAY

- 251 (0xfb)

Key name VK_ZOOM