

# Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

## Rocky Enterprise Linux 9.2 Manual Pages on command 'fgetpwent\_r.3'

## \$ man fgetpwent\_r.3

GETPWENT\_R(3)

Linux Programmer's Manual

GETPWENT\_R(3)

#### NAME

getpwent\_r, fgetpwent\_r - get passwd file entry reentrantly

#### SYNOPSIS

#include <pwd.h>

int getpwent\_r(struct passwd \*pwbuf, char \*buf,

size\_t buflen, struct passwd \*\*pwbufp);

int fgetpwent\_r(FILE \*stream, struct passwd \*pwbuf, char \*buf,

size\_t buflen, struct passwd \*\*pwbufp);

Feature Test Macro Requirements for glibc (see feature\_test\_macros(7)):

getpwent\_r(),

Since glibc 2.19:

\_DEFAULT\_SOURCE

Glibc 2.19 and earlier:

\_BSD\_SOURCE || \_SVID\_SOURCE

fgetpwent\_r():

Since glibc 2.19:

\_DEFAULT\_SOURCE

Glibc 2.19 and earlier:

\_SVID\_SOURCE

## DESCRIPTION

The functions getpwent\_r() and fgetpwent\_r() are the reentrant versions of getpwent(3) and

fgetpwent(3). The former reads the next passwd entry from the stream initialized by setp?

went(3). The latter reads the next passwd entry from stream.

The passwd structure is defined in <pwd.h> as follows:

struct passwd {

/\* username \*/ char \*pw\_name; \*pw passwd; /\* user password \*/ char uid t pw uid; /\* user ID \*/ /\* group ID \*/ gid\_t pw\_gid; char \*pw\_gecos; /\* user information \*/ char \*pw\_dir; /\* home directory \*/ char \*pw shell; /\* shell program \*/

};

For more information about the fields of this structure, see passwd(5).

The nonreentrant functions return a pointer to static storage, where this static storage contains further pointers to user name, password, gecos field, home directory and shell. The reentrant functions described here return all of that in caller-provided buffers. First of all there is the buffer pwbuf that can hold a struct passwd. And next the buffer buf of size buflen that can hold additional strings. The result of these functions, the struct passwd read from the stream, is stored in the provided buffer \*pwbuf, and a pointer to this struct passwd is returned in \*pwbufp.

#### **RETURN VALUE**

On success, these functions return 0 and \*pwbufp is a pointer to the struct passwd. On error, these functions return an error value and \*pwbufp is NULL.

#### ERRORS

ENOENT No more entries.

ERANGE Insufficient buffer space supplied. Try again with larger buffer.

## ATTRIBUTES

For an explanation of the terms used in this section, see attributes(7).

?

?

?Interface ? Attribute ? Value

?getpwent\_r() ? Thread safety ? MT-Unsafe race:pwent locale ?

?fgetpwent\_r() ? Thread safety ? MT-Safe

Page 2/4

#### 

In the above table, pwent in race:pwent signifies that if any of the functions setpwent(),

getpwent(), endpwent(), or getpwent\_r() are used in parallel in different threads of a

program, then data races could occur.

#### CONFORMING TO

These functions are GNU extensions, done in a style resembling the POSIX version of func?

tions like getpwnam\_r(3). Other systems use the prototype

struct passwd \*

getpwent\_r(struct passwd \*pwd, char \*buf, int buflen);

or, better,

```
int
```

getpwent\_r(struct passwd \*pwd, char \*buf, int buflen,

FILE \*\*pw\_fp);

## NOTES

The function getpwent\_r() is not really reentrant since it shares the reading position in

the stream with all other threads.

#### EXAMPLES

#define \_GNU\_SOURCE

#include <pwd.h>

#include <stdio.h>

#include <stdint.h>

#define BUFLEN 4096

int

main(void)

## {

struct passwd pw;

struct passwd \*pwp;

char buf[BUFLEN];

int i;

setpwent();

while (1) {

i = getpwent\_r(&pw, buf, sizeof(buf), &pwp);

```
break;
```

printf("%s (%jd)\tHOME %s\tSHELL %s\n", pwp->pw\_name,

```
(intmax_t) pwp->pw_uid, pwp->pw_dir, pwp->pw_shell);
```

```
}
```

```
endpwent();
```

```
exit(EXIT_SUCCESS);
```

}

SEE ALSO

fgetpwent(3), getpw(3), getpwent(3), getpwnam(3), getpwuid(3), putpwent(3), passwd(5) COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.

GNU

2020-11-01

GETPWENT\_R(3)