

Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

# Rocky Enterprise Linux 9.2 Manual Pages on command 'getfsfile.3'

### \$ man getfsfile.3

int

};

fs passno;

GETFSENT(3) Linux Programmer's Manual GETFSENT(3) NAME getfsent, getfsspec, getfsfile, setfsent, endfsent - handle fstab entries **SYNOPSIS** #include <fstab.h> void endfsent(void); struct fstab \*getfsent(void); struct fstab \*getfsfile(const char \*mount point); struct fstab \*getfsspec(const char \*special\_file); int setfsent(void); **DESCRIPTION** These functions read from the file /etc/fstab. The struct fstab is defined by: struct fstab { /\* block device name \*/ char \*fs\_spec; char \*fs\_file; /\* mount point \*/ char \*fs vfstype; /\* file-system type \*/ /\* mount options \*/ char \*fs mntops; const char \*fs\_type; /\* rw/rq/ro/sw/xx option \*/ int fs\_freq; /\* dump frequency, in days \*/

/\* pass number on parallel dump \*/

Here the field fs\_type contains (on a \*BSD system) one of the five strings "rw", "rq",

"ro", "sw", "xx" (read-write, read-write with quota, read-only, swap, ignore).

Page 1/3

The function setfsent() opens the file when required and positions it at the first line.

The function getfsent() parses the next line from the file. (After opening it when re? quired.)

The function endfsent() closes the file when required.

The function getfsspec() searches the file from the start and returns the first entry found for which the fs\_spec field matches the special\_file argument.

The function getfsfile() searches the file from the start and returns the first entry found for which the fs\_file field matches the mount\_point argument.

### **RETURN VALUE**

Upon success, the functions getfsent(), getfsfile(), and getfsspec() return a pointer to a struct fstab, while setfsent() returns 1. Upon failure or end-of-file, these functions return NULL and 0, respectively.

#### **ATTRIBUTES**

For an explanation of the terms used in this section, see attributes(7). ? ?Interface ? Attribute ? Value ?endfsent(), ? Thread safety ? MT-Unsafe race:fsent ? ? ?setfsent() ? ?getfsent(), ? Thread safety ? MT-Unsafe race:fsent locale ? ?getfsspec(), ? ? ? ?getfsfile() ? 

#### **CONFORMING TO**

These functions are not in POSIX.1. Several operating systems have them, for example, \*BSD, SunOS, Digital UNIX, AIX (which also has a getfstype()). HP-UX has functions of the same names, that however use a struct checklist instead of a struct fstab, and calls these functions obsolete, superseded by getmntent(3).

#### **NOTES**

These functions are not thread-safe.

Since Linux allows mounting a block special device in several places, and since several devices can have the same mount point, where the last device with a given mount point is

the interesting one, while getfsfile() and getfsspec() only return the first occurrence, these two functions are not suitable for use under Linux.

## SEE ALSO

getmntent(3), fstab(5)

### COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.

GNU 2017-09-15 GETFSENT(3)