

Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

# Rocky Enterprise Linux 9.2 Manual Pages on command 'inet\_addr.3'

## \$ man inet\_addr.3

INET(3) Linux Programmer's Manual INET(3) NAME inet\_aton, inet\_addr, inet\_network, inet\_ntoa, inet\_makeaddr, inet\_lnaof, inet\_netof - In? ternet address manipulation routines **SYNOPSIS** #include <sys/socket.h> #include <netinet/in.h> #include <arpa/inet.h> int inet\_aton(const char \*cp, struct in\_addr \*inp); in\_addr\_t inet\_addr(const char \*cp); in\_addr\_t inet\_network(const char \*cp); char \*inet\_ntoa(struct in\_addr in); struct in\_addr inet\_makeaddr(in\_addr\_t net, in\_addr\_t host); in\_addr\_t inet\_lnaof(struct in\_addr in); in\_addr\_t inet\_netof(struct in\_addr in); Feature Test Macro Requirements for glibc (see feature test macros(7)): inet\_aton(), inet\_ntoa(): Since glibc 2.19: \_DEFAULT\_SOURCE In glibc up to and including 2.19:

### **DESCRIPTION**

\_BSD\_SOURCE || \_BSD\_SOURCE

into binary form (in network byte order) and stores it in the structure that inp points to. inet\_aton() returns nonzero if the address is valid, zero if not. The address sup? plied in cp can have one of the following forms:

- a.b.c.d Each of the four numeric parts specifies a byte of the address; the bytes are assigned in left-to-right order to produce the binary address.
- a.b.c Parts a and b specify the first two bytes of the binary address. Part c is in? terpreted as a 16-bit value that defines the rightmost two bytes of the binary address. This notation is suitable for specifying (outmoded) Class B network addresses.
- a.b Part a specifies the first byte of the binary address. Part b is interpreted as a 24-bit value that defines the rightmost three bytes of the binary address.This notation is suitable for specifying (outmoded) Class A network addresses.
- a The value a is interpreted as a 32-bit value that is stored directly into the binary address without any byte rearrangement.

In all of the above forms, components of the dotted address can be specified in decimal, octal (with a leading 0), or hexadecimal, with a leading 0X). Addresses in any of these forms are collectively termed IPV4 numbers-and-dots notation. The form that uses exactly four decimal numbers is referred to as IPv4 dotted-decimal notation (or sometimes: IPv4 dotted-quad notation).

inet\_aton() returns 1 if the supplied string was successfully interpreted, or 0 if the string is invalid (errno is not set on error).

The inet\_addr() function converts the Internet host address cp from IPv4 numbers-and-dots notation into binary data in network byte order. If the input is invalid, INADDR\_NONE (usually -1) is returned. Use of this function is problematic because -1 is a valid ad? dress (255.255.255.255). Avoid its use in favor of inet\_aton(), inet\_pton(3), or getad? drinfo(3), which provide a cleaner way to indicate error return.

The inet\_network() function converts cp, a string in IPv4 numbers-and-dots notation, into a number in host byte order suitable for use as an Internet network address. On success, the converted address is returned. If the input is invalid, -1 is returned.

The inet\_ntoa() function converts the Internet host address in, given in network byte or? der, to a string in IPv4 dotted-decimal notation. The string is returned in a statically allocated buffer, which subsequent calls will overwrite.

The inet\_lnaof() function returns the local network address part of the Internet address

in. The returned value is in host byte order.

The inet\_netof() function returns the network number part of the Internet address in. The returned value is in host byte order.

The inet\_makeaddr() function is the converse of inet\_netof() and inet\_lnaof(). It returns an Internet host address in network byte order, created by combining the network number net with the local address host, both in host byte order.

The structure in\_addr as used in inet\_ntoa(), inet\_makeaddr(), inet\_lnaof(), and inet\_netof() is defined in <netinet/in.h> as:

```
typedef uint32_t in_addr_t;
struct in_addr {
   in_addr_t s_addr;
};
```

#### **ATTRIBUTES**

For an explanation of the terms used in this section, see attributes(7).

?Interface ? Attribute ? Value ?

?inet aton(), inet addr(), ? Thread safety ? MT-Safe locale ?

?inet\_network(), inet\_ntoa() ? ? ?

?inet\_makeaddr(), inet\_lnaof(), ? Thread safety ? MT-Safe ?

?inet\_netof() ? ? ?

#### **CONFORMING TO**

inet\_addr(), inet\_ntoa(): POSIX.1-2001, POSIX.1-2008, 4.3BSD.

inet\_aton() is not specified in POSIX.1, but is available on most systems.

## NOTES

On x86 architectures, the host byte order is Least Significant Byte first (little endian), whereas the network byte order, as used on the Internet, is Most Significant Byte first (big endian).

inet\_lnaof(), inet\_netof(), and inet\_makeaddr() are legacy functions that assume they are dealing with classful network addresses. Classful networking divides IPv4 network ad? dresses into host and network components at byte boundaries, as follows:

- Class A This address type is indicated by the value 0 in the most significant bit of the (network byte ordered) address. The network address is contained in the most significant byte, and the host address occupies the remaining three bytes.
- Class B This address type is indicated by the binary value 10 in the most significant two bits of the address. The network address is contained in the two most sig? nificant bytes, and the host address occupies the remaining two bytes.
- Class C This address type is indicated by the binary value 110 in the most significant three bits of the address. The network address is contained in the three most significant bytes, and the host address occupies the remaining byte.

Classful network addresses are now obsolete, having been superseded by Classless Inter-Do? main Routing (CIDR), which divides addresses into network and host components at arbitrary bit (rather than byte) boundaries.

#### **EXAMPLES**

An example of the use of inet\_aton() and inet\_ntoa() is shown below. Here are some exam? ple runs:

```
$ ./a.out 226.000.000.037 # Last byte is in octal
    226.0.0.31
    $ ./a.out 0x7f.1
                             # First byte is in hex
    127.0.0.1
Program source
  #define _BSD_SOURCE
  #include <arpa/inet.h>
  #include <stdio.h>
  #include <stdlib.h>
  int
  main(int argc, char *argv[])
    struct in_addr addr;
    if (argc != 2) {
       fprintf(stderr, "%s <dotted-address>\n", argv[0]);
       exit(EXIT_FAILURE);
    }
```

if  $(inet\_aton(argv[1], \&addr) == 0) {$ 

```
fprintf(stderr, "Invalid address\n");
    exit(EXIT_FAILURE);
}
printf("%s\n", inet_ntoa(addr));
exit(EXIT_SUCCESS);
}
SEE ALSO
byteorder(3), getaddrinfo(3), gethostbyname(3), getnameinfo(3), getnetent(3), inet_net_pton(3), inet_ntop(3), inet_pton(3), hosts(5), networks(5)
COLOPHON
```

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.

GNU 2020-12-21 INET(3)