



Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'ipptoolfile.5'

\$ man ipptoolfile.5

ipptoolfile(5) OpenPrinting ipptoolfile(5)

NAME

ipptoolfile - ipptool file format

DESCRIPTION

The ipptool(1) program accepts free-form plain text files that describe one or more IPP requests. Comments start with the "#" character and continue to the end of the line.

Each request is enclosed by curly braces, for example:

```
# This is a comment
{
# The name of the test
NAME "Print PDF File"
# The request to send
OPERATION Print-Job
GROUP operation-attributes-tag
ATTR charset attributes-charset utf-8
ATTR language attributes-natural-language en
ATTR uri printer-uri $uri
ATTR name requesting-user-name $user
ATTR mimeMediaType document-format application/pdf
GROUP job-attributes-tag
ATTR collection media-col {
# US Letter plain paper from the "main" tray
MEMBER collection media-size {
```

```
MEMBER integer x-dimension 21590
MEMBER integer y-dimension 27940
}
MEMBER integer media-top-margin 423
MEMBER integer media-bottom-margin 423
MEMBER integer media-left-margin 423
MEMBER integer media-right-margin 423
MEMBER keyword media-source "main"
MEMBER keyword media-type "stationery"
}
FILE testfile.pdf
# The response to expect
STATUS successful-ok
EXPECT job-id OF-TYPE integer WITH-VALUE >0
EXPECT job-uri OF-TYPE uri
}
{
# The name of the test
NAME "Wait for Job to Complete"
# The request to send
OPERATION Get-Job-Attributes
GROUP operation-attributes-tag
ATTR charset attributes-charset utf-8
ATTR language attributes-natural-language en
ATTR uri printer-uri $uri
ATTR integer job-id $job-id
ATTR name requesting-user-name $user
# The response to expect
STATUS successful-ok
EXPECT job-id OF-TYPE integer WITH-VALUE $job-id
EXPECT job-uri OF-TYPE uri
EXPECT job-state OF-TYPE enum WITH-VALUE >5 REPEAT-NO-MATCH
EXPECT job-originating-user-name OF-TYPE name WITH-VALUE "$user"
```

```
# Show the job state until completed...
```

```
DISPLAY job-state
```

```
DISPLAY job-state-reasons
```

```
}
```

TOP-LEVEL DIRECTIVES

The following directives can be used outside of a test:

```
{ test }
```

Defines a test.

```
DEFINE variable-name value
```

Defines the named variable to the given value. This is equivalent to specifying `-d variable-name=value` on the `ipptool(8)` command-line.

```
DEFINE-DEFAULT variable-name value
```

Defines the named variable to the given value if it does not already have a value.

```
FILE-ID "identifier"
```

Specifies an identifier string for the current file.

```
IGNORE-ERRORS yes
```

```
IGNORE-ERRORS no
```

Specifies whether, by default, `ipptool(8)` will ignore errors and continue with subsequent tests.

```
INCLUDE "filename"
```

```
INCLUDE <filename>
```

Includes another test file. The first form includes a file relative to the current test file, while the second form includes a file from the `ipptool(8)` include directory.

```
INCLUDE-IF-DEFINED name "filename"
```

```
INCLUDE-IF-DEFINED name <filename>
```

Includes another test file if the named variable is defined. The first form includes a file relative to the current test file, while the second form includes a file from the `ipptool(8)` include directory.

```
INCLUDE-IF-NOT-DEFINED name "filename"
```

```
INCLUDE-IF-NOT-DEFINED name <filename>
```

Includes another test file if the named variable is not defined. The first form includes a file relative to the current test file, while the second form includes a

file from the `ipptool(8)` include directory.

`SKIP-IF-DEFINED` variable-name

`SKIP-IF-NOT-DEFINED` variable-name

Specifies that the remainder of the test file should be skipped when the variable is or is not defined.

`STOP-AFTER-INCLUDE-ERROR` no

`STOP-AFTER-INCLUDE-ERROR` yes

Specifies whether tests will be stopped after an error in an included file.

`TRANSFER` auto

Specifies that tests will, by default, use "Transfer-Encoding: chunked" for requests with attached files and "Content-Length:" for requests without attached files.

`TRANSFER` chunked

Specifies that tests will, by default, use the HTTP/1.1 "Transfer-Encoding: chunked" header. This is the default and is equivalent to specifying `-c` on the `ipptool(8)` command-line. Support for chunked requests is required for conformance with all versions of IPP.

`TRANSFER` length

Specifies that tests will, by default, use the HTTP/1.0 "Content-Length:" header. This is equivalent to specifying `-l` on the `ipptool(8)` command-line. Support for content length requests is required for conformance with all versions of IPP.

`VERSION` 1.0

`VERSION` 1.1

`VERSION` 2.0

`VERSION` 2.1

`VERSION` 2.2

Specifies the default IPP version number to use for the tests that follow.

TEST DIRECTIVES

The following directives are understood within a test:

`ATTR` out-of-band-tag attribute-name

`ATTR` tag attribute-name value(s)

Adds an attribute to the test request. Out-of-band tags (`admin-define`, `delete-attribute`, `no-value`, `not-settable`, `unknown`, `unsupported`) have no value. Values for other tags are delimited by the comma (",") character - escape commas using the "\" character?

ter. Common attributes and values are listed in the IANA IPP registry - see references below.

ATTR collection attribute-name { MEMBER tag member-name value(s) ... } [... , { ... }]

Adds a collection attribute to the test request. Member attributes follow the same syntax as regular attributes and can themselves be nested collections. Multiple collection values can be supplied as needed, separated by commas.

COMPRESSION deflate

COMPRESSION gzip

COMPRESSION none

Uses the specified compression on the document data following the attributes in a Print-Job or Send-Document request.

DELAY seconds[,repeat-seconds]

Specifies a delay in seconds before this test will be run. If two values are specified, the second value is used as the delay between repeated tests.

DISPLAY attribute-name

Specifies that value of the named attribute should be output as part of the test report.

EXPECT attribute-name [predicate(s)]

EXPECT ?attribute-name predicate(s)

EXPECT !attribute-name

Specifies that the response must/may/must not include the named attribute. Additional requirements can be added as predicates - see the "EXPECT PREDICATES" section for more information on predicates. Attribute names can specify member attributes by separating the attribute and member names with the forward slash, for example "media-col/media-size/x-dimension".

EXPECT-ALL attribute-name [predicate(s)]

EXPECT-ALL ?attribute-name predicate(s)

Specifies that the response must/may include the named attribute and that all occurrences of that attribute must match the given predicates.

FILE filename

Specifies a file to include at the end of the request. This is typically used when sending a test print file.

GROUP tag

Specifies the group tag for subsequent attributes in the request.

IGNORE-ERRORS yes

IGNORE-ERRORS no

Specifies whether ipptool(8) will ignore errors and continue with subsequent tests.

MONITOR-PRINTER-STATE [printer-uri] { EXPECT attribute-name [predicate(s)] }

Specifies printer state monitoring tests to run in parallel with the test operation.

The monitoring tests will run until all of the EXPECT conditions are satisfied or the primary test operation has completed, whichever occurs first.

NAME "literal string"

Specifies the human-readable name of the test.

OPERATION operation-code

Specifies the operation to be performed.

PASS-IF-DEFINED variable-name

PASS-IF-NOT-DEFINED variable-name

Specifies that the current test should be passed automatically when the variable is or is not defined.

PAUSE "message"

Displays the provided message and waits for the user to press a key to continue.

REQUEST-ID number

REQUEST-ID random

Specifies the request-id value to use in the request, either an integer or the word "random" to use a randomly generated value (the default).

RESOURCE path

Specifies an alternate resource path that is used for the HTTP POST request. The default is the resource from the URI provided to the ipptool(8) program.

SKIP-IF-DEFINED variable-name

SKIP-IF-NOT-DEFINED variable-name

Specifies that the current test should be skipped when the variable is or is not defined.

SKIP-PREVIOUS-ERROR yes

SKIP-PREVIOUS-ERROR no

Specifies whether ipptool(8) will skip the current test if the previous test resulted in an error/failure.

STATUS status-code [predicate]

Specifies an expected response status-code value. Additional requirements can be added as predicates - see the "STATUS PREDICATES" section for more information on predicates.

TEST-ID "identifier"

Specifies an identifier string for the current test.

TRANSFER auto

Specifies that this test will use "Transfer-Encoding: chunked" if it has an attached file or "Content-Length:" otherwise.

TRANSFER chunked

Specifies that this test will use the HTTP/1.1 "Transfer-Encoding: chunked" header.

TRANSFER length

Specifies that this test will use the HTTP/1.0 "Content-Length:" header.

VERSION 1.0

VERSION 1.1

VERSION 2.0

VERSION 2.1

VERSION 2.2

Specifies the IPP version number to use for this test.

EXPECT PREDICATES

The following predicates are understood following the EXPECT test directive:

COUNT number

Requires the EXPECT attribute to have the specified number of values.

DEFINE-MATCH variable-name

Defines the variable to "1" when the EXPECT condition matches. A side-effect of this predicate is that this EXPECT will never fail a test.

DEFINE-NO-MATCH variable-name

Defines the variable to "1" when the EXPECT condition does not match. A side-effect of this predicate is that this EXPECT will never fail a test.

DEFINE-VALUE variable-name

Defines the variable to the value of the attribute when the EXPECT condition matches.

A side-effect of this predicate is that this EXPECT will never fail a test.

DISPLAY-MATCH "message"

Displays the specified message when the EXPECT condition matches.

IF-DEFINED variable-name

Makes the EXPECT conditions apply only if the specified variable is defined.

IF-NOT-DEFINED variable-name

Makes the EXPECT conditions apply only if the specified variable is not defined.

IN-GROUP tag

Requires the EXPECT attribute to be in the specified group tag.

OF-TYPE tag[(limits)|tag...]

Requires the EXPECT attribute to use one of the specified value tag(s). Most value tags also support the specification of limits in parenthesis, for example "name(42)" would allow nameWith/WithoutLanguage strings up to 42 octets in length, "name(4:MAX)" would allow nameWith/WithoutLanguage strings between 4 and 255 octets in length, and "integer(-273:MAX)" would allow integers between -273 and 2147483647.

REPEAT-LIMIT number

Specifies the maximum number of times to repeat if the REPEAT-MATCH or REPEAT-NO-MATCH predicate is specified. The default value is 1000.

REPEAT-MATCH

REPEAT-NO-MATCH

Specifies that the current test should be repeated when the EXPECT condition matches or does not match.

SAME-COUNT-AS attribute-name

Requires the EXPECT attribute to have the same number of values as the specified par? allele attribute.

WITH-ALL-HOSTNAMES "literal string"

WITH-ALL-HOSTNAMES "/regular expression/"

Requires that all URI values contain a matching hostname.

WITH-ALL-RESOURCES "literal string"

WITH-ALL-RESOURCES "/regular expression/"

Requires that all URI values contain a matching resource (including leading /).

WITH-ALL-SCHEMES "literal string"

WITH-ALL-SCHEMES "/regular expression/"

Requires that all URI values contain a matching scheme.

WITH-ALL-VALUES "literal string"

Requires that all values of the EXPECT attribute match the literal string. Comparisons are case-sensitive.

WITH-ALL-VALUES <number

WITH-ALL-VALUES =number

WITH-ALL-VALUES >number

WITH-ALL-VALUES number[,...,number]

Requires that all values of the EXPECT attribute match the number(s) or numeric comparison. When comparing rangeOfInteger values, the "<" and ">" operators only check the upper bound of the range.

WITH-ALL-VALUES "false"

WITH-ALL-VALUES "true"

Requires that all values of the EXPECT attribute match the boolean value given.

WITH-ALL-VALUES "/regular expression/"

Requires that all values of the EXPECT attribute match the regular expression, which must conform to the POSIX regular expression syntax. Comparisons are case-sensitive.

WITH-DISTINCT-VALUES

Requires that all values of the EXPECT attribute are unique. Comparisons are case-sensitive. Only charset, collection, enum, integer, keyword, mimeType, naturalLanguage, rangeOfInteger, resolution, uriScheme attributes support this predicate.

WITH-HOSTNAME "literal string"

WITH-HOSTNAME "/regular expression/"

Requires that at least one URI value contains a matching hostname.

WITH-RESOURCE "literal string"

WITH-RESOURCE "/regular expression/"

Requires that at least one URI value contains a matching resource (including leading /).

WITH-SCHEME "literal string"

WITH-SCHEME "/regular expression/"

Requires that at least one URI value contains a matching scheme.

WITH-VALUE "literal string"

Requires that at least one value of the EXPECT attribute matches the literal string. Comparisons are case-sensitive.

WITH-VALUE <number

WITH-VALUE =number

WITH-VALUE >number

WITH-VALUE number[,...,number]

Requires that at least one value of the EXPECT attribute matches the number(s) or numeric comparison. When comparing rangeOfInteger values, the "<" and ">" operators only check the upper bound of the range.

WITH-VALUE "false"

WITH-VALUE "true"

Requires that at least one value of the EXPECT attribute matches the boolean value given.

WITH-VALUE "/regular expression/"

Requires that at least one value of the EXPECT attribute matches the regular expression, which must conform to the POSIX regular expression syntax. Comparisons are case-sensitive.

WITH-VALUE-FROM attribute-name

Requires that the value(s) of the EXPECT attribute matches the value(s) in the specified attribute. For example, "EXPECT job-sheets WITH-VALUE-FROM job-sheets-supported" requires that the "job-sheets" value is listed as a value of the "job-sheets-supported" attribute.

STATUS PREDICATES

The following predicates are understood following the STATUS test directive:

DEFINE-MATCH variable-name

Defines the variable to "1" when the STATUS matches. A side-effect of this predicate is that this STATUS will never fail a test.

DEFINE-NO-MATCH variable-name

Defines the variable to "1" when the STATUS does not match. A side-effect of this predicate is that this STATUS will never fail a test.

IF-DEFINED variable-name

Makes the STATUS apply only if the specified variable is defined.

IF-NOT-DEFINED variable-name

Makes the STATUS apply only if the specified variable is not defined.

REPEAT-LIMIT number

Specifies the maximum number of times to repeat. The default value is 1000.

REPEAT-MATCH

REPEAT-NO-MATCH

Specifies that the current test should be repeated when the response status-code matches or does not match the value specified by the STATUS directive.

OPERATION CODES

Operation codes correspond to the hexadecimal numbers (0xHHHH) and names from RFC 8011 and other IPP extension specifications. Here is a complete list of names supported by ipp?

tool(8):

Acknowledge-Document

Acknowledge-Identify-Printer

Acknowledge-Job

Activate-Printer

Add-Document-Images

Allocate-Printer-Resources

Cancel-Current-Job

Cancel-Job

Cancel-Jobs

Cancel-My-Jobs

Cancel-Resource

Cancel-Subscription

Close-Job

Create-Job

Create-Job-Subscriptions

Create-Printer

Create-Printer-Subscriptions

Create-Resource

Create-Resource-Subscriptions

Create-System-Subscriptions

CUPS-Accept-Jobs

CUPS-Accept-Jobs

CUPS-Add-Modify-Class

CUPS-Add-Modify-Printer

CUPS-Authenticate-Job

CUPS-Create-Local-Printer
CUPS-Delete-Class
CUPS-Delete-Printer
CUPS-Get-Classes
CUPS-Get-Default
CUPS-Get-Devices
CUPS-Get-Document
CUPS-Get-PPD
CUPS-Get-PPDs
CUPS-Get-Printers
CUPS-Move-Job
CUPS-Reject-Jobs
CUPS-Set-Default
Deactivate-Printer
Deallocate-Printer-Resources
Delete-Printer
Deregister-Output-Device
Disable-All-Printers
Disable-Printer
Enable-All-Printers
Enable-Printer
Fetch-Document
Fetch-Job
Get-Job-Attributes
Get-Jobs
Get-Next-Document-Data
Get-Notifications
Get-Output-Device-Attributes
Get-Printer-Attributes
Get-Printer-Support-Files
Get-Printer-Supported-Values
Get-Printers
Get-Subscription-Attributes

Get-Subscriptions
Get-System-Attributes
Get-System-Supported-Values
Hold-Job
Hold-New-Jobs
Identify-Printer
Install-Resource
Pause-All-Printers
Pause-All-Printers-After-Current-Job
Pause-Printer
Pause-Printer-After-Current-Job
Print-Job
Print-URI
Promote-Job
Purge-Jobs
Register-Output-Device
Release-Held-New-Jobs
Release-Job
Renew-Subscription
Reprocess-Job
Restart-Job
Restart-Printer
Restart-System
Resubmit-Job
Resume-All-Printers
Resume-Job
Resume-Printer
Schedule-Job-After
Send-Document
Send-Hardcopy-Document
Send-Notifications
Send-Resource-Data
Send-URI

Set-Job-Attributes
Set-Printer-Attributes
Set-Resource-Attributes
Set-System-Attributes
Shutdown-All-Printers
Shutdown-One-Printer
Shutdown-Printer
Startup-All-Printers
Startup-One-Printer
Startup-Printer
Suspend-Current-Job
Update-Active-Jobs
Update-Document-Status
Update-Job-Status
Update-Output-Device-Attributes
Validate-Document
Validate-Job

STATUS CODES

Status codes correspond to the hexadecimal numbers (0xHHHH) and names from RFC 8011 and other IPP extension specifications. Here is a complete list of the names supported by ipp?

tool(8):

client-error-account-authorization-failed
client-error-account-closed
client-error-account-info-needed
client-error-account-limit-reached
client-error-attributes-not-settable
client-error-attributes-or-values-not-supported
client-error-bad-request
client-error-charset-not-supported
client-error-compression-error
client-error-compression-not-supported
client-error-conflicting-attributes
client-error-document-access-error

client-error-document-format-error
client-error-document-format-not-supported
client-error-document-password-error
client-error-document-permission-error
client-error-document-security-error
client-error-document-unprintable-error
client-error-forbidden
client-error-gone
client-error-ignored-all-notifications
client-error-ignored-all-subscriptions
client-error-not-authenticated
client-error-not-authorized
client-error-not-fetchable
client-error-not-found
client-error-not-possible
client-error-print-support-file-not-found
client-error-request-entity-too-large
client-error-request-value-too-long
client-error-timeout
client-error-too-many-subscriptions
client-error-uri-scheme-not-supported
cups-error-account-authorization-failed
cups-error-account-closed
cups-error-account-info-needed
cups-error-account-limit-reached
cups-see-other
redirection-other-site
server-error-busy
server-error-device-error
server-error-internal-error
server-error-job-canceled
server-error-multiple-document-jobs-not-supported
server-error-not-accepting-jobs

server-error-operation-not-supported
server-error-printer-is-deactivated
server-error-service-unavailable
server-error-temporary-error
server-error-version-not-supported
successful-ok
successful-ok-but-cancel-subscription
successful-ok-conflicting-attributes
successful-ok-events-complete
successful-ok-ignored-notifications
successful-ok-ignored-or-substituted-attributes
successful-ok-ignored-subscriptions
successful-ok-too-many-events

TAGS

Value and group tags correspond to the names from RFC 8011 and other IPP extension specifications. Here are the group tags:

document-attributes-tag
event-notification-attributes-tag
job | job-attributes-tag
operation | operation-attributes-tag
printer | printer-attributes-tag
resource-attributes-tag
subscription-attributes-tag
system-attributes-tag
unsupported-attributes-tag

Here are the value tags:

admin-define
boolean
charset
collection | begCollection
dateTime
default
delete-attribute

enum
integer
keyword
language | naturalLanguage
mimetype | mimeMediaType
name | nameWithLanguage | nameWithoutLanguage
no-value
not-settable
octetString
rangeOfInteger
resolution
text | textWithLanguage | textWithoutLanguage
unknown
unsupported
uri
uriScheme

VARIABLES

The ipptool(8) program maintains a list of variables that can be used in any literal string or attribute value by specifying "\$variable-name". Aside from variables defined using the -d option or DEFINE directive, the following pre-defined variables are available:

\$\$ Inserts a single "\$" character.

\$ENV[name]

Inserts the value of the named environment variable, or an empty string if the environment variable is not defined.

\$date-current

Inserts the current date and time using the ISO-8601 format ("yyyy-mm-ddThh:mm:ssZ").

\$date-start

Inserts the starting date and time using the ISO-8601 format ("yyyy-mm-ddThh:mm:ssZ").

\$filename

Inserts the filename provided to ipptool(8) with the -f option.

\$filetype

Inserts the MIME media type for the filename provided to ipptool(8) with the -f option.

tion.

\$hostname

Inserts the hostname from the URI provided to ipptool(8).

\$job-id

Inserts the last "job-id" attribute value returned in a test response or 0 if no "job-id" attribute has been seen.

\$job-uri

Inserts the last "job-uri" attribute value returned in a test response or an empty string if no "job-uri" attribute has been seen.

\$notify-subscription-id

Inserts the last "notify-subscription-id" attribute value returned in a test response or 0 if no "notify-subscription-id" attribute has been seen.

\$port

Inserts the port number from the URI provided to ipptool(8).

\$resource

Inserts the resource path from the URI provided to ipptool(8).

\$scheme

Inserts the scheme from the URI provided to ipptool(8).

\$uri Inserts the URI provided to ipptool(8).

\$uriuser

Inserts the username from the URI provided to ipptool(8), if any.

\$user

Inserts the current user's login name.

SEE ALSO

ipptool(1), IANA IPP Registry (<https://www.iana.org/assignments/ipp-registrations>), PWG Internet Printing Protocol Workgroup (<https://www.pwg.org/ipp>), RFC 8011 (<https://data?tracker.ietf.org/doc/html/rfc8011>)

COPYRIGHT

Copyright ? 2021-2022 by OpenPrinting.

2021-09-20

CUPS

ipptoolfile(5)