

Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

# Rocky Enterprise Linux 9.2 Manual Pages on command 'Igammaf.3'

\$ man Igammaf.3 LGAMMA(3) Linux Programmer's Manual LGAMMA(3) NAME Igamma, Igammaf, Igammal, Igamma\_r, Igammaf\_r, Igammal\_r, signgam - log gamma function **SYNOPSIS** #include <math.h> double lgamma(double x); float Igammaf(float x); long double lgammal(long double x); double Igamma\_r(double x, int \*signp); float lgammaf\_r(float x, int \*signp); long double lgammal\_r(long double x, int \*signp); extern int signgam; Link with -lm. Feature Test Macro Requirements for glibc (see feature\_test\_macros(7)): Igamma(): \_ISOC99\_SOURCE || \_POSIX\_C\_SOURCE >= 200112L || \_XOPEN\_SOURCE || /\* Since glibc 2.19: \*/ \_DEFAULT\_SOURCE || /\* Glibc versions <= 2.19: \*/ \_BSD\_SOURCE || \_SVID\_SOURCE lgammaf(), lgammal(): \_ISOC99\_SOURCE || \_POSIX\_C\_SOURCE >= 200112L || /\* Since glibc 2.19: \*/ \_DEFAULT\_SOURCE || /\* Glibc versions <= 2.19: \*/ \_BSD\_SOURCE || \_SVID\_SOURCE lgamma\_r(), lgammaf\_r(), lgammal\_r():

```
/* Since glibc 2.19: */ _DEFAULT_SOURCE || /* Glibc versions <= 2.19: */ _BSD_SOURCE || _SVID_SOURCE signgam:
```

### \_XOPEN\_SOURCE

|| /\* Since glibc 2.19: \*/ \_DEFAULT\_SOURCE

|| /\* Glibc versions <= 2.19: \*/ \_BSD\_SOURCE || \_SVID\_SOURCE

#### **DESCRIPTION**

For the definition of the Gamma function, see tgamma(3).

The Igamma(), Igammaf(), and Igammal() functions return the natural logarithm of the abso? Iute value of the Gamma function. The sign of the Gamma function is returned in the ex? ternal integer signgam declared in <math.h>. It is 1 when the Gamma function is positive or zero, -1 when it is negative.

Since using a constant location signgam is not thread-safe, the functions lgamma\_r(), lgammaf\_r(), and lgammal\_r() have been introduced; they return the sign via the argument signp.

# **RETURN VALUE**

On success, these functions return the natural logarithm of Gamma(x).

If x is a NaN, a NaN is returned.

If x is 1 or 2, +0 is returned.

If x is positive infinity or negative infinity, positive infinity is returned.

If x is a nonpositive integer, a pole error occurs, and the functions return +HUGE\_VAL, +HUGE\_VALF, or +HUGE\_VALL, respectively.

If the result overflows, a range error occurs, and the functions return HUGE\_VAL, HUGE\_VALF, or HUGE\_VALL, respectively, with the correct mathematical sign.

# **ERRORS**

See math\_error(7) for information on how to determine whether an error has occurred when calling these functions.

The following errors can occur:

Pole error: x is a nonpositive integer

errno is set to ERANGE (but see BUGS). A divide-by-zero floating-point exception (FE\_DIVBYZERO) is raised.

Range error: result overflow

raised.

# **CONFORMING TO**

The Igamma() functions are specified in C99, POSIX.1-2001, and POSIX.1-2008. signgam is specified in POSIX.1-2001 and POSIX.1-2008, but not in C99. The Igamma\_r() functions are nonstandard, but present on several other systems.

# **BUGS**

In glibc 2.9 and earlier, when a pole error occurs, errno is set to EDOM; instead of the POSIX-mandated ERANGE. Since version 2.10, glibc does the right thing.

# SEE ALSO

tgamma(3)

# **COLOPHON**

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.

2017-09-15

LGAMMA(3)