



Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'strerrorname_np.3'

\$ man strerrorname_np.3

STRERROR(3) Linux Programmer's Manual STRERROR(3)

NAME

strerror, strerrorname_np, strerrordesc_np, strerror_r, strerror_l - return string describing error number

SYNOPSIS

```
#include <string.h>

char *strerror(int errnum);

const char *strerrorname_np(int errnum);

const char *strerrordesc_np(int errnum);

int strerror_r(int errnum, char *buf, size_t buflen);

/* XSI-compliant */

char *strerror_r(int errnum, char *buf, size_t buflen);

/* GNU-specific */

char *strerror_l(int errnum, locale_t locale);
```

Feature Test Macro Requirements for glibc (see feature_test_macros(7)):

strerrorname_np(), strerrordesc_np():

 _GNU_SOURCE

strerror_r():

 The XSI-compliant version is provided if:

 (_POSIX_C_SOURCE >= 200112L) && ! _GNU_SOURCE

 Otherwise, the GNU-specific version is provided.

DESCRIPTION

The strerror() function returns a pointer to a string that describes the error code passed

in the argument `errnum`, possibly using the `LC_MESSAGES` part of the current locale to select the appropriate language. (For example, if `errnum` is `EINVAL`, the returned description will be "Invalid argument".) This string must not be modified by the application, but may be modified by a subsequent call to `strerror()` or `strerror_l()`. No other library function, including `perror(3)`, will modify this string.

Like `strerror()`, the `strerrordesc_np()` function returns a pointer to a string that describes the error code passed in the argument `errnum`, with the difference that the returned string is not translated according to the current locale.

The `strerrorname_np()` function returns a pointer to a string containing the name of the error code passed in the argument `errnum`. For example, given `EPERM` as an argument, this function returns a pointer to the string "EPERM".

`strerror_r()`

The `strerror_r()` function is similar to `strerror()`, but is thread safe. This function is available in two versions: an XSI-compliant version specified in POSIX.1-2001 (available since `glibc 2.3.4`, but not POSIX-compliant until `glibc 2.13`), and a GNU-specific version (available since `glibc 2.0`). The XSI-compliant version is provided with the feature test macros settings shown in the SYNOPSIS; otherwise the GNU-specific version is provided. If no feature test macros are explicitly defined, then (since `glibc 2.4`) `_POSIX_C_SOURCE` is defined by default with the value `200112L`, so that the XSI-compliant version of `strerror_r()` is provided by default.

The XSI-compliant `strerror_r()` is preferred for portable applications. It returns the error string in the user-supplied buffer `buf` of length `buflen`.

The GNU-specific `strerror_r()` returns a pointer to a string containing the error message. This may be either a pointer to a string that the function stores in `buf`, or a pointer to some (immutable) static string (in which case `buf` is unused). If the function stores a string in `buf`, then at most `buflen` bytes are stored (the string may be truncated if `buflen` is too small and `errnum` is unknown). The string always includes a terminating null byte (`'\0'`).

`strerror_l()`

`strerror_l()` is like `strerror()`, but maps `errnum` to a locale-dependent error message in the locale specified by `locale`. The behavior of `strerror_l()` is undefined if `locale` is the special locale object `LC_GLOBAL_LOCALE` or is not a valid locale object handle.

The `strerror()`, `strerror_l()`, and the GNU-specific `strerror_r()` functions return the appropriate error description string, or an "Unknown error nnn" message if the error number is unknown.

On success, `strerrorname_np()` and `strerrordesc_np()` return the appropriate error description string. If `errnum` is an invalid error number, these functions return `NULL`.

The XSI-compliant `strerror_r()` function returns 0 on success. On error, a (positive) error number is returned (since glibc 2.13), or -1 is returned and `errno` is set to indicate the error (glibc versions before 2.13).

POSIX.1-2001 and POSIX.1-2008 require that a successful call to `strerror()` or `strerror_l()` shall leave `errno` unchanged, and note that, since no function return value is reserved to indicate an error, an application that wishes to check for errors should initialize `errno` to zero before the call, and then check `errno` after the call.

ERRORS

EINVAL The value of `errnum` is not a valid error number.

ERANGE Insufficient storage was supplied to contain the error description string.

VERSIONS

The `strerror_l()` function first appeared in glibc 2.6.

ATTRIBUTES

For an explanation of the terms used in this section, see [attributes\(7\)](#).

??

?Interface ? Attribute ? Value ?

??

?`strerror()` ? Thread safety ? MT-Unsafe race:`strerror` ?

??

?`strerrorname_np()`, ? Thread safety ? MT-Safe ?

?`strerrordesc_np()` ? ? ?

??

?`strerror_r()`, ? Thread safety ? MT-Safe ?

?`strerror_l()` ? ? ?

??

CONFORMING TO

`strerror()` is specified by POSIX.1-2001, POSIX.1-2008, C89, and C99. `strerror_r()` is specified by POSIX.1-2001 and POSIX.1-2008.

strerror_l() is specified in POSIX.1-2008.

The GNU-specific functions strerror_r(), strerrorname_np(), and strerrordesc_np() are non-standard extensions.

POSIX.1-2001 permits strerror() to set errno if the call encounters an error, but does not specify what value should be returned as the function result in the event of an error. On some systems, strerror() returns NULL if the error number is unknown. On other systems, strerror() returns a string something like "Error nnn occurred" and sets errno to EINVAL if the error number is unknown. C99 and POSIX.1-2008 require the return value to be non-NULL.

NOTES

The GNU C Library uses a buffer of 1024 characters for strerror(). This buffer size therefore should be sufficient to avoid an ERANGE error when calling strerror_r().

strerrorname_np() and strerrordesc_np() are thread-safe and async-signal-safe.

SEE ALSO

err(3), errno(3), error(3), perror(3), strsignal(3), locale(7)

COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <https://www.kernel.org/doc/man-pages/>.

2020-11-01

STRERROR(3)