



*Full credit is given to the above companies including the OS that this PDF file was generated!*

## **Red Hat Enterprise Linux Release 9.2 Manual Pages on 'getnetent.3' command**

**\$ man getnetent.3**

GETNETENT(3)      Linux Programmer's Manual      GETNETENT(3)

### **NAME**

getnetent, getnetbyname, getnetbyaddr, setnetent, endnetent - get net?

work entry

### **SYNOPSIS**

```
#include <netdb.h>

struct netent *getnetent(void);

struct netent *getnetbyname(const char *name);

struct netent *getnetbyaddr(uint32_t net, int type);

void setnetent(int stayopen);

void endnetent(void);
```

### **DESCRIPTION**

The getnetent() function reads the next entry from the networks data?

base and returns a netent structure containing the broken-out fields  
from the entry. A connection is opened to the database if necessary.

The getnetbyname() function returns a netent structure for the entry  
from the database that matches the network name.

The getnetbyaddr() function returns a netent structure for the entry  
from the database that matches the network number net of type type.

The net argument must be in host byte order.

The setnetent() function opens a connection to the database, and sets  
the next entry to the first entry. If stayopen is nonzero, then the  
connection to the database will not be closed between calls to one of

the getnet\*() functions.

The endnetent() function closes the connection to the database.

The netent structure is defined in <netdb.h> as follows:

```
struct netent {  
    char    *n_name; /* official network name */  
    char    **n_aliases; /* alias list */  
    int     n_addrtype; /* net address type */  
    uint32_t n_net; /* network number */  
}
```

The members of the netent structure are:

n\_name The official name of the network.

n\_aliases

A NULL-terminated list of alternative names for the network.

n\_addrtype

The type of the network number; always AF\_INET.

n\_net The network number in host byte order.

## RETURN VALUE

The getnetent(), getnetbyname(), and getnetbyaddr() functions return a pointer to a statically allocated netent structure, or a null pointer if an error occurs or the end of the file is reached.

## FILES

/etc/networks

networks database file

## ATTRIBUTES

For an explanation of the terms used in this section, see at?

tributes(7).

??

?Interface ? Attribute ? Value ?

??

?getnetent() ? Thread safety ? MT-Unsafe race:netent ?

? ? ? race:netentbuf env locale ?

??

?getnetbyname() ? Thread safety ? MT-Unsafe race:netbyname ?

In the above table, netent in race:netent signifies that if any of the functions setnetent(), getnetent(), or endnetent() are used in parallel in different threads of a program, then data races could occur.

## CONFORMING TO

POSIX.1-2001, POSIX.1-2008, 4.3BSD.

## NOTES

In glibc versions before 2.2, the net argument of `getnetbyaddr()` was of type long.

#### SEE ALSO

getnetent\_r(3), getprotoent(3), getservent(3)

RFC 1101

## COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at  
<https://www.kernel.org/doc/man-pages/>.

GNU 2020-12-21 GETNETENT(3)