

Full credit is given to the above companies including the OS that this PDF file was generated!

# Red Hat Enterprise Linux Release 9.2 Manual Pages on 'pam\_pwhistory.8' command

### \$ man pam\_pwhistory.8

PAM\_PWHISTORY(8)

Linux-PAM Manual

PAM\_PWHISTORY(8)

NAME

pam\_pwhistory - PAM module to remember last passwords

**SYNOPSIS** 

pam\_pwhistory.so [debug] [use\_authtok] [enforce\_for\_root] [remember=N]

[retry=N] [authtok\_type=STRING]

[conf=/path/to/config-file]

#### **DESCRIPTION**

This module saves the last passwords for each user in order to force password change history and keep the user from alternating between the same password too frequently.

This module does not work together with kerberos. In general, it does not make much sense to use this module in conjunction with NIS or LDAP, since the old passwords are stored on the local machine and are not available on another machine for password history checking.

### **OPTIONS**

debug

Turns on debugging via syslog(3).

use\_authtok

When password changing enforce the module to use the new password provided by a previously stacked password module (this is used in the example of the stacking of the pam\_passwdqc module documented below).

Page 1/3

```
enforce for root
```

If this option is set, the check is enforced for root, too.

#### remember=N

The last N passwords for each user are saved. The default is 10.

Value of 0 makes the module to keep the existing contents of the opasswd file unchanged.

## retry=N

Prompt user at most N times before returning with error. The default is 1.

### authtok\_type=STRING

See pam\_get\_authtok(3) for more details.

conf=/path/to/config-file

Use another configuration file instead of the default

/etc/security/pwhistory.conf.

The options for configuring the module behavior are described in the pwhistory.conf(5) manual page. The options specified on the module command line override the values from the configuration file.

### MODULE TYPES PROVIDED

Only the password module type is provided.

#### **RETURN VALUES**

#### PAM\_AUTHTOK\_ERR

No new password was entered, the user aborted password change or new password couldn't be set.

### PAM\_IGNORE

Password history was disabled.

#### PAM MAXTRIES

Password was rejected too often.

### PAM\_USER\_UNKNOWN

User is not known to system.

#### **EXAMPLES**

An example password section would be:

#%PAM-1.0

password required pam\_pwhistory.so

password required pam\_unix.so use\_authtok

In combination with pam\_passwdqc:

#%PAM-1.0

password required pam\_passwdqc.so config=/etc/passwdqc.conf

password required pam\_pwhistory.so use\_authtok

password required pam\_unix.so use\_authtok

**FILES** 

/etc/security/opasswd

File with password history

SEE ALSO

pwhistory.conf(5), pam.conf(5), pam.d(5), pam(8) pam\_get\_authtok(3)

**AUTHOR** 

pam\_pwhistory was written by Thorsten Kukuk <kukuk@thkukuk.de>

Linux-PAM Manual 11/29/2022 PAM\_PWHISTORY(8)