



Full credit is given to the above companies including the OS that this PDF file was generated!

Red Hat Enterprise Linux Release 9.2 Manual Pages on 'pthread_setcanceltype.3' command

\$ man pthread_setcanceltype.3

PTHREAD_SETCANCELSTATE(3) Linux Programmer's Manual PTHREAD_SETCANCELSTATE(3)

NAME

pthread_setcancelstate, pthread_setcanceltype - set cancelability state and type

SYNOPSIS

```
#include <pthread.h>

int pthread_setcancelstate(int state, int *oldstate);

int pthread_setcanceltype(int type, int *oldtype);

Compile and link with -pthread.
```

DESCRIPTION

The pthread_setcancelstate() sets the cancelability state of the calling thread to the value given in state. The previous cancelability state of the thread is returned in the buffer pointed to by oldstate.

The state argument must have one of the following values:

PTHREAD_CANCEL_ENABLE

The thread is cancelable. This is the default cancelability state in all new threads, including the initial thread. The thread's cancelability type determines when a cancelable thread will respond to a cancellation request.

PTHREAD_CANCEL_DISABLE

The thread is not cancelable. If a cancellation request is received, it is blocked until cancelability is enabled.

The pthread_setcanceltype() sets the cancelability type of the calling

thread to the value given in type. The previous cancelability type of the thread is returned in the buffer pointed to by oldtype. The type argument must have one of the following values:

PTHREAD_CANCEL_DEFERRED

A cancellation request is deferred until the thread next calls a function that is a cancellation point (see pthreads(7)). This is the default cancelability type in all new threads, including the initial thread.

Even with deferred cancellation, a cancellation point in an asynchronous signal handler may still be acted upon and the effect is as if it was an asynchronous cancellation.

PTHREAD_CANCEL_ASYNCCHRONOUS

The thread can be canceled at any time. (Typically, it will be canceled immediately upon receiving a cancellation request, but the system doesn't guarantee this.)

The set-and-get operation performed by each of these functions is atomic with respect to other threads in the process calling the same function.

RETURN VALUE

On success, these functions return 0; on error, they return a nonzero error number.

ERRORS

The pthread_setcancelstate() can fail with the following error:

EINVAL Invalid value for state.

The pthread_setcanceltype() can fail with the following error:

EINVAL Invalid value for type.

ATTRIBUTES

For an explanation of the terms used in this section, see attributes(7).

??

?Interface ? Attribute ? Value ?

??

?pthread_setcancelstate(), ? Thread safety ? MT-Safe ?

One of the few circumstances in which asynchronous cancelability is useful is for cancellation of a thread that is in a pure compute-bound loop.

Portability notes

The Linux threading implementations permit the `oldstate` argument of `pthread_setcancelstate()` to be `NULL`, in which case the information about the previous cancelability state is not returned to the caller.

Many other implementations also permit a `NULL` `oldstat` argument, but POSIX.1 does not specify this point, so portable applications should always specify a non-`NULL` value in `oldstate`. A precisely analogous set of statements applies for the `oldtype` argument of `pthread_setcancel?`
`type()`.

EXAMPLES

See `pthread_cancel(3)`.

SEE ALSO

`pthread_cancel(3)`, `pthread_cleanup_push(3)`, `pthread_testcancel(3)`,
`pthreads(7)`

COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <https://www.kernel.org/doc/man-pages/>.

Linux 2020-06-09 PTHREAD_SETCANCELSTATE(3)